



Ahsay Offsite Backup Server

v6

Administrator's Guide

Ahsay Systems Co. Ltd.

30 May 2011

Ahsay Offsite Backup Server

Administrator's Guide

Copyright Notice

© 2011 Ahsay Systems Co. Ltd. All rights reserved.

The use and copying of this product is subject to a license agreement. Any other use is prohibited. No part of this publication may be reproduced, transmitted, transcribed, stored in a retrieval system or translated into any language in any form by any means without prior written consent of Ahsay Systems Co. Ltd. Information in this manual is subject to change without notice and does not represent a commitment on the part of the vendor, Ahsay Systems Co. Ltd. does not warrant that this document is error free. If you find any errors in this document, please report to Ahsay Systems Co. Ltd. in writing.

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).

Trademarks

Ahsay, Ahsay Online Backup Suite, Ahsay Offsite Backup Server, Ahsay Online Backup Manager, Ahsay A-Click Backup, Ahsay Replication Server, Ahsay BackupBox Firmware, Ahsay Universal Backup System, Ahsay NAS Client Utility are trademarks of Ahsay Systems Corporation Limited.

Microsoft, Windows, Microsoft Exchange Server and Microsoft SQL Server are registered trademarks of Microsoft Corporation.

Sun, Solaris, SPARC, JAVA and Java Runtime Environment are registered trademarks of Sun Microsystems Inc.

Oracle, Oracle 8i, Oracle 9i, Oracle 10g, Oracle 11g are registered trademarks of Oracle Corporation.

Lotus, Domino, Notes are registered trademark of IBM Corporation.

Red Hat is registered trademark of Linus Torvalds.

Apple and Mac OS X are registered trademarks of Apple Computer, Inc.

All other product names are registered trademarks of their respective owners.

Disclaimer

Ahsay Systems Co. Ltd. will not have or accept any liability, obligation or responsibility whatsoever for any loss, destruction or damage (including without limitation consequential loss, destruction or damage) however arising from or in respect of any use or misuse of reliance on this document. By reading and following the instructions in this document, you agree to accept unconditionally the terms of this Disclaimer and as they may be revised and/or amended from time to time by Ahsay Systems Co. Ltd. without prior notice to you.

Revision History

Date	Descriptions
8 April 2011	First revision for AhsayOBS v6.3 Release
30 May 2011	New: 4.17 Use Windows Event Log 15 Multiple Thread Support 16 Create a "Read Only" or Non Admin System User Updated: 9.1 My Profile / Edit System User

Table of Contents

1	Overview.....	1
1.1	Conventions	1
1.2	Definitions, Acronyms and Abbreviation	1
1.3	System Requirements.....	3
2	Quick Start	4
2.1	Getting started.....	4
3	Best Practices and Recommendations	8
3.1	AhsayOBS Hardware Requirements.....	8
3.2	AhsayOBS Server Configuration.....	8
3.3	AhsayOBS Java Heap Size Setting.....	9
3.4	AhsayOBS QPS Settings	9
3.5	Maximum Number of Users on AhsayOBS	9
3.6	Use a Static IP Address.....	10
3.7	Scheduling of Backup Jobs on AhsayOBS.....	10
3.8	Enable Replication on AhsayOBS	10
3.9	AhsayOBS Server Scaling	10
3.10	Anti-Virus Software on AhsayOBS.....	11
3.11	Enable CRC Checking	11
3.12	Running AhsayOBS as a non-root user	11
3.13	Expose only TCP port 80 and 443 to the public	11
3.14	Restricting Access on Administration Panel.....	11
3.15	System Resources	11
3.16	AhsayOBS File System Tuning.....	12
3.17	Network Load Balancing Configuration.....	12
3.18	AhsayOBS Reseller Panel and AhsayRDR	12
4	Server Configuration.....	13
4.1	User Languages Setting	16
4.2	System Login Name/Password	18
4.3	Host Name	18
4.4	System Home, Policy Home and User Home Directories	19
4.5	Single Level Access.....	19
4.6	Email System Setting.....	20
4.7	Proxy Setting.....	20
4.8	Windows Active Directory (AD) Authentication Setting.....	21
4.9	Redirector.....	21
4.10	Language Setting	21
4.11	Features Setting.....	22
4.12	Permission Updated Files	23
4.13	Moved Files	23
4.14	Auto User Home Allocation	23
4.15	Welcome Email.....	23
4.16	Free Trial Setting	24
4.17	Use Windows Event Log	25
5	Software License.....	26
5.1	Licensee Name and License Key.....	29
5.2	Automatic License Renewal	29
5.3	Evaluation Expiry and Free Edition.....	30

5.4	Offline License Activation.....	33
5.5	License Management Portal.....	35
6	Managing Routine Job	36
6.1	Backup Report	38
6.2	Online Restore Report.....	38
6.3	Setting Change Report	38
6.4	Missed Backup Report.....	38
6.5	Inactive User Report	39
6.6	Off-line Backup Reminder.....	39
6.7	Backup Quota Reminder.....	39
6.8	Trial User Reminder	39
6.9	Usage Report.....	40
6.10	Error Report	40
6.11	Replication Error Report.....	40
6.12	Inactive User Removal.....	40
6.13	Retention Policy.....	41
6.14	Rebuild User Storage	41
6.15	System Log Removal.....	42
6.16	Debug Log Removal	42
6.17	Cyclic Redundancy Check (CRC) Checking.....	42
7	Managing Replication.....	44
8	Managing Other Options.....	45
8.1	In-File Delta Settings for all AhsayACB users.....	46
8.2	Block Size	46
8.3	Minimum Size.....	47
8.4	Delta Merge	47
8.5	In-File Delta Type.....	47
8.6	Upload Full File	48
8.7	Adgroups.....	49
8.8	Advertisements	49
9	Manage System User (Reseller Panel).....	53
9.1	My Profile / Edit System User	53
9.2	SMTP Settings	55
9.3	Customize Interface	55
9.4	Add System User	57
9.5	List / Remove System User.....	57
10	Managing Backup Users	59
10.1	Create Backup User	59
10.2	List / Remove Backup User	60
10.3	Broadcast messages to backup users.....	62
10.4	Managing User Profile.....	64
10.5	Managing Backup Set.....	67
10.6	Initiating Backup from AhsayOBS.....	69
10.7	Browsing User Backup File.....	71
10.8	Reviewing User Backup Report.....	72
10.9	Reviewing User Storage Statistics.....	73
10.10	User Log.....	74
11	Group Policy Management	75
11.1	About Group Policy	75
11.2	Best Practices for using Group Policy	77

11.3	Group Policy Limitations and Restrictions.....	78
11.3.1	List Policy Control.....	79
11.4	User Group.....	81
11.4.1	List User.....	81
11.4.2	Manage User Group.....	82
11.5	Policy Group.....	88
11.5.1	Manage Policy Group.....	88
11.5.2	Shared Quota Policy.....	90
11.5.3	Backup Set Setting Policy.....	92
11.5.4	Backup User Policy Control.....	95
11.5.5	Global Filter Policy.....	98
11.5.6	Shared Backup User Policy.....	99
11.5.7	System Users Policy Control.....	100
12	Delta Merge Technology.....	102
12.1	Introduction.....	102
12.2	Delta Merge Policy.....	102
12.3	Delta Merge Process.....	102
12.4	Delta Merge Queue.....	104
12.5	Limitations.....	104
12.6	Delta Merge Examples.....	105
13	Account Lockout.....	108
13.1	Configuration.....	108
13.2	Account Lockout Rules.....	109
13.3	Unlocking Accounts.....	110
13.4	Account Lockout on AhsayOBS/AhsayRDR.....	111
13.5	Account Lockout on AhsayOBM/AhsayACB.....	112
13.6	Account Lockout Auditing.....	113
14	Multiple Thread Support.....	114
15	Create a “Read Only” or Non Admin System User.....	115
16	AutoUpdate.....	116
16.1	How it works.....	116
16.2	Using AutoUpdate.....	116
16.3	Customizing AutoUpdate.....	116
16.4	Forcing an extra AutoUpdate.....	117
16.5	AutoUpdate Limitations.....	117
17	Backup / Restore files using off-line media.....	118
17.1	Seed loading backup files (Import).....	118
17.2	Saving backup files to off-line media (Export).....	119
18	High Availability & Load-Balancing Configuration.....	120
19	Secure Socket Layer (SSL) Configuration.....	121
19.1	Installing a trusted SSL certificate.....	121
19.2	Enforcing SSL to the web interface.....	124
20	Monitoring System Activities.....	126
20.1	Reviewing System Log.....	126
20.2	Reviewing Backup Log.....	127
20.3	Reviewing Restored File Log.....	128
20.4	Reviewing Backup Error log.....	129
20.5	Reviewing Replication Log.....	130
20.6	Reviewing Advertisement Log.....	131
21	Branding AhsayOBM & AhsayACB.....	132

21.1	Customization Portal.....	132
22	Branding AhsayOBS.....	133
22.1	Welcome Page	133
22.2	Different welcome pages for different domains	133
22.3	Customizing the company logo displayed	133
22.4	Customizing the Look and Feel of the web interface	136
22.5	Customizing all text of the web interface	137
22.6	Customizing email reports	137
22.7	Localizing the software.....	138
23	Advanced Configuration.....	139
23.1	Listening to non-standard TCP/IP Port.....	139
23.2	Listening to a single IP address	140
23.3	Restricting access to system page by IP address	141
24	External API References.....	143
24.1	Overview.....	143
24.2	Limitations	143
24.3	IP Restrictions.....	143
24.4	User Authorization.....	146
24.5	Adding User	147
24.6	Modifying User Profile	149
24.7	Deleting User	152
24.8	Listing Users	153
24.9	Getting User Information.....	155
24.10	Adding a Backup Set	157
24.11	Deleting a Backup Set.....	158
24.12	Listing Backup Sets	159
24.13	Get Backup Set	160
24.14	Updating a Backup Set.....	167
24.15	Listing Backup Jobs.....	168
24.16	Listing Backup Job Status.....	170
24.17	Getting Backup Job Report.....	172
24.18	Getting Backup Job Report Summary	174
24.19	Listing Backup Files	176
24.20	Getting User Storage Statistics	177
24.21	Listing User Storage	179
24.22	Get License	181
24.23	Get Replication Mode.....	183
24.24	Send Forgot Password Email.....	184
24.25	Delete Backup File.....	185
24.26	Add Advertisement	186
24.27	List Advertisements	187
24.28	Modify Advertisement	188
24.29	Delete Advertisement.....	189
24.30	Add AdGroup.....	190
24.31	List AdGroups.....	190
24.32	Modify AdGroup	191
24.33	Delete AdGroup	192
24.34	Run Backup.....	193
24.35	Get Backup Job Progress	194
24.36	Add User Group.....	196

24.37	List User Group.....	197
24.38	Modify User Group.....	199
24.39	Delete User Group	200
24.40	List Policy Groups	201
24.41	Add User Groups to Policy Group.....	206
24.42	Delete User Group from Policy Group	208
24.43	Additional APIs	208
25	Further Information.....	209
Appendix.....		210
Appendix A	Supported Language Code.....	210
Appendix B	Supported Time zone	211
Appendix C	Product Documentations.....	213
Appendix D	Error Code 1011 and 1012.....	214

1 Overview

1.1 Conventions

A list of notations that are used throughout this document.

Convention	Descriptions	Example
Bold	Important Information	WARNING: You must check the timestamp of obrA.jar before proceeding to step2.
<i>Italic</i>	Folder Path or File Path	<i>/usr/local/obs/conf</i>
[]	Graphical Interface Elements	[Manage Log]
%%	Filepath in Windows format	%OBSR_HOME%
\$	Filepath in Linux/Unix/BSD format	\$OBSR_HOME
<i>italic</i>	Command	<i>mkdir /usr/local/obs</i>

Notation that are used specifically for API section:

Convention	Descriptions
<Text Inside angle brackets>	Placeholder for which you must supply a value.
[Text inside square brackets]	Optional items.
{Text insides braces}	Set of required items; choose one.
Vertical bar ()	Separator for mutually exclusive items; choose one.
Ellipsis (...)	Items that can be repeated.

1.2 Definitions, Acronyms and Abbreviation

Term/Abbreviation	Definition
AhsayOBS	Ahsay™ Offsite Backup Server
AhsayRPS	Ahsay™ Replication Server
AhsayRDR	Ahsay™ Redirector Server
AhsayOBM	Ahsay™ Online Backup Manager
AhsayACB	Ahsay™ A-Click Backup
OBSR_HOME	The install location of AhsayOBS & AhsayRPS.

	<p><u>Windows</u> <i>C:\Program Files\AhsayOBS and AhsayRPS</i></p> <p><u>Linux/FreeBSD/Solaris</u> <i>/usr/local/obs/</i></p>
OBSR_HOME_BAK	<p>The backup location of AhsayOBS & AhsayRPS. It is used temporary during the install/upgrade process.</p> <p><u>Windows</u> <i>C:\Program Files\AhsayOBS and AhsayRPS.bak\</i></p> <p><u>Linux/FreeBSD/Solaris</u> <i>/usr/local/obs.bak/</i></p>
CONF_HOME	<p>The backup location of AhsayOBS & AhsayRPS. It is used temporary during the install/upgrade process.</p> <p><u>Windows</u> <i>%OBSR_HOME%\conf</i></p> <p><u>Linux/FreeBSD/Solaris</u> <i>\$OBSR_HOME/conf</i></p>
USER_HOMES	<p>The directories where AhsayOBS and AhsayRPS store the AhsayOBM & AhsayACB users accounts.</p> <p>The default location is: <i>%OBSR_HOME%\users</i></p>
POLICY_HOME	<p>The directory where AhsayOBS and AhsayRPS store its system users and group policy information.</p> <p><u>Windows</u> <i>%OBSR_HOME%\system\policy</i></p> <p><u>Linux/FreeBSD/Solaris</u> <i>\$OBSR_HOME\system\policy</i></p>
SYSTEM_HOME	<p>The directory where AhsayOBS and AhsayRPS store its system information.</p> <p><u>Windows</u> <i>%OBSR_HOME%\system\</i></p> <p><u>Linux/FreeBSD/Solaris</u> <i>\$OBSR_HOME\system\</i></p>
WEBAPPS_HOME	<p>Location of the webapps directory inside the installation directory of AhsayOBS & AhsayRPS.</p>

	<p><u>Windows</u> <i>%OBSR_HOME%\webapps.</i></p> <p><u>Linux/FreeBSD/Solaris</u> <i>\$OBSR_HOME\webapps</i></p>
WEBAPP_HOME_BAK	<p>A backup of the webapps directory inside AhsayOBS and AhsayRPS.</p> <p><u>Windows</u> <i>%OBSR_HOME%\webapps.bak</i></p> <p><u>Linux/FreeBSD/Solaris</u> <i>\$OBSR_HOME\webapps.bak</i></p>
RECEIVER_HOME	<p>The location where the replicated data is stored for a particular replication receiver.</p>
JAVA_HOME	<p>The location where JAVA is installed</p>

1.3 System Requirements

Please refer to the [AhsayPedia Article #2165](#) for system requirements of AhsayOBS v6.

It is recommended to install AhsayOBS on server grade O/S and hardware platform. However, for evaluation purposes installation on Windows XP or Windows 7 platforms would be fine for testing.

2 Quick Start

This chapter describes the minimum steps required to start using AhsayOBS. Please consult the information in the following chapters for a complete reference to all features available in AhsayOBS.


2.1 Getting started

To setup your AhsayOBS, please do the followings:


Setup Your Backup Server

1. Point your browser to `http://<your-obs-server>`.
2. Login as AhsayOBS administrator.

The default login name and password are "system" and "system" respectively.



3. Set your hostname.



Enter a resolvable hostname for your backup server (e.g. backup.your-company.com) into the [Host Name] text field. Although you can supply an IP address here, it is preferable to use a hostname instead.

If you are using custom TCP port for HTTP/HTTPS connection (i.e. non 80 or 443), you need to append the custom port number to the [Host Name] field.

e.g. backup.yourcompany.com:8080

If you are not using custom TCP port, open a browser on the backup server and type in the value of [Host Name] as an URL and check if you get the backup server homepage. If you are not able to connect to the webpage, please try until you can reach it and put this value in the [Host Name] field.

4. Set the [User Homes] directory.

[User Homes] refers to directories where AhsayOBS stores the backup files and backup log for all its users. You should set [User Homes] to directories where there are lots of free spaces.

5. Set your SMTP Server.

Enter a resolvable hostname (or an IP address) of your SMTP server into the [SMTP Server] text field.

If your SMTP server is not running on standard SMTP ports (i.e. port 25), you can append your custom port number to your SMTP server address to use this server e.g. mail.your-company.com:8025.

You are only required to enter the [Login Name] and [Password] if your SMTP server enquires user authentication when sending emails.

6. Press the [Update] button.
7. Enter your license key (You can skip this step if you are evaluating this software).

Enter the licensing information printed on [End User License Agreement] printout into the text field provided in the [Manage System] -> [Software License] panel. Please note that both [Licensee Name] and [License Key] are case sensitive.


Note:

By default AhsayOBS service listens to port 80 for http and port 443 for https. Please make sure your servers firewall is configured to allow incoming access via these ports.

Add Backup User

You need to add backup user to the system before you can start backing up data to AhsayOBS. To add a backup user to the system, please do the followings:

1. Click the [Manage User] link available at the top menu and choose [Add user].
2. Enter the user information for the new user account into the form provided.



Key	Description
Login Name	Login Name of the new account.
Password	Password of the new account.
Alias	Another name of the new account.

Time zone	Time zone of the new account
Language	Preferred language for email report of the new account.
Backup Client	Choose AhsayOBM client or AhsayACB client.
Advertise Group	Choose whether advertisements are displayed at the bottom of the AhsayOBM/AhsayACB client
Type	<p>Trial User – Account of this type will be deleted from the system after an inactivity period of 30 days by default.</p> <p>Paid User – Account of this type will stay within the system until it is removed from the system by administrator.</p>
Email	Email address of the new account.
Welcome email	Check this option to send a welcome email to the user.
User Home	The top directory where the software stores backup files and all other information for the new account.
Backup Quota	Backup Quota of the new account.
Bandwidth	Bandwidth throttling for this user account.
Add-on modules	Add-on modules for this user account.

3. Press the [Add] button to create the user.
4. The account is now ready.

Login and Run Backup

1. Point your browser to <http://<your-obs-server>/>.
2. Click the [User Login] link at the top.
3. Login with the login name and password you have created in previous section.
4. Follow the [Quick Start] information available in the User's Guide to install the AhsayOBM or AhsayACB onto users computer to start backing up data.

3 Best Practices and Recommendations

This chapter lists out all best practices and recommendations which you should consider before deploying AhsayOBS to a production environment.

3.1 AhsayOBS Hardware Requirements

AhsayOBS should be installed on a machine supporting 64 bit multiple CPU and multiple cores. A 64 bit Operating System will allow AhsayOBS to run on a 64 bit Java JRE platform, as 64 bit Java is capable of supporting larger Java heap size settings. This type of configuration will provide sufficient capacity for future business expansion, to meet the needs of existing customers, and to support new AhsayOBS server features.

A more powerful machine will also reduce the need for frequent hardware upgrades, which will require service down time for data migration.

It is a good idea to ensure your AhsayOBS server is equipped with some redundancy features, i.e power supply, network card, and is connect it to a UPS (Uninterruptible Power Supply).

3.2 AhsayOBS Server Configuration

One of the most important factors in determining backup and restore performance is the disk performance of your AhsayOBS server. Poor backup and restore performance can be attributed to:

- i. The use of network drives for AhsayOBS system and user homes.
- ii. The use of a single large disk or volume for multiple AhsayOBS user homes
- iii. Inadequate balancing of the disk I/O across multiple physical drives

To improve performance of your AhsayOBS server, you should consider using:

- i. A separate drive dedicated for your O/S installation
- ii. A separate local dedicated for your AhsayOBS installation home
- iii. A separate local drive for each individual AhsayOBS user home
- iv. A separate local drive for AhsayOBS system home
- v. Distribute user accounts across multiple user homes to balance the I/O load
- vi. Your AhsayOBS service should be running on a dedicated machine

It is not recommended to use the O/S partition or drive as the AhsayOBS system or user home. If the O/S partition runs out of space, this will cause your O/S to become unstable and may even crash your AhsayOBS server.

3.3 AhsayOBS Java Heap Size Setting

Due to features such as CRC checking, delta merging, support for image, Hyper-V, VMware backupsets AhsayOBS v6 may require more Java memory. Although, there is no exact formula for calculating the correct Java heap size setting for any given AhsayOBS server. In general a Java heap size setting of at least 2048M is recommended, assuming AhsayOBS is running on a 64 bit Operating System.

3.4 AhsayOBS QPS Settings

To ensure user accounts are evenly distributed across your user home drives. It is recommended you configure your QPS settings, this can be done via your AhsayOBS web console under [Manage System] -> [Server Configuration] -> [Auto User Home Allocation]. The QPS settings for each user home drive should not be set to "unlimited" or "Not Used".

For AhsayOBS servers with multiple user homes, you should consider a QPS setting of 50% to 70% for each user home drive. This will prevent user accounts being concentrated onto one drive, which may cause the drive to run out of disk space very easily. This could result in data corruption on the affected user home(s).

Also, an even distribution of user accounts across your AhsayOBS user homes will improve backup performance, by spreading the disk I/O load.

3.5 Maximum Number of Users on AhsayOBS

There is no exact formula for calculating the maximum number of user accounts on for any AhsayOBS server. As it is dependent on many factors such as but not limited to:

- i. AhsayOBS server hardware
- ii. The composition or mix of users accounts, i.e. AhsayOBM or AhsayACB users
- iii. The number of backupsets per a user account
- iv. The type of backupsets per user account
- v. The backup behavior of each user

Also, AhsayOBM/AhsayACB v6 clients are enhanced to utilize multiple threads for backup and restore. It is recommended to keep this number to around 300 user accounts, to avoid potential performance problems.

3.6 Use a Static IP Address

The use of dynamic IP addresses for AhsayOBS domain names may result in an unstable backup service whenever the IP address re-cycles.

A static IP address will ensure the remote IP address sent by AhsayOBS to the Ahsay license server will remain the same during daily routine license checks. This will avoid potential license errors, i.e. 1011 or 1012 license errors which could result of the automatic shutdown of your AhsayOBS service.

It is strongly recommended to use a static IP address for your AhsayOBS server to ensure a stable and reliable backup service.

3.7 Scheduling of Backup Jobs on AhsayOBS

To improve overall backup performance we recommend that scheduled backup jobs (by default starts at 09:00pm) should not be confined to a few start times.

The start times of scheduled backup jobs should be evenly distributed throughout the day to avoid potential performance bottlenecks on your AhsayOBS server.

3.8 Enable Replication on AhsayOBS

To ensure you have a backup of your AhsayOBS server in the event of any hardware issues. We recommend enabling replication on your AhsayOBS server to a separate AhsayRPS server.

3.9 AhsayOBS Server Scaling

To cope with business and or data growth, instead of upgrading to new hardware to support additional users and data, which may involve a lengthy data migration process.

Your backup service capacity can be upgraded using an AhsayRDR solution. The advantage of using AhsayRDR is it allows you to expand your backup service easily by adding new AhsayOBS servers to the current setup with minimal interruption to your backup service.

WARNING:

AhsayRDR does not support AhsayOBS member servers which are configured with Reseller Panel settings.

3.10 Anti-Virus Software on AhsayOBS

If you have anti-virus software installed on your AhsayOBS server, please make sure the user home and system home drives are excluded from scanning, as this may interfere with normal AhsayOBS operation.

3.11 Enable CRC Checking

It is strongly recommended the CRC checking on AhsayOBS is enabled to ensure the integrity of the backup files.

3.12 Running AhsayOBS as a non-root user

If you are running AhsayOBS on Linux, you are advised to run the AhsayOBS service as non-root user. (AhsayOBS service is run under root by default). This minimizes the impact of damages that could be done on the system in case the system has been compromised by hackers.

3.13 Expose only TCP port 80 and 443 to the public

It is recommended to expose only TCP port 80 and 443 to the public on your firewall. Please consult the user's manual of your firewall for more information on how to do so.

3.14 Restricting Access on Administration Panel

For security reasons, we would recommend that the Administration Panel of AhsayOBS/AhsayRPS must be hidden from public access, i.e. it should be exposed to local area network only.

3.15 System Resources

Extra system resources may required for the following backup set types:

- Windows System Backup
- Windows 2008 System State
- Shadow Protect
- Microsoft Exchange
- Microsoft SQL Server
- Oracle Database
- Lotus Domino Server
- VMware ESX/ESXi
- VMware Server
- Microsoft Hyper V

In most cases, the file size of a single file in these backup set types are large, therefore extra system resources (such as memory and disk space) are required for using the delta merging feature. For user homes containing backupsets with delta merge enabled. It is recommended to maintain at least 30% to 40% free disk space.

3.16 AhsayOBS File System Tuning

In order to ensure optimal performance from an AhsayOBS server file system, please ensure that you:

1. Use local drives instead of network drives, i.e. iSCSi, NFS, SAMBA etc
2. Tune your file system. For example, for NTFS, run the followings:

```
fsutil behavior set disable8dot3 1
fsutil behavior set mftzone 2
fsutil behavior set disablelastaccess 1
fsutil behavior set memoryusage 2
```

3. Turn off drive indexing [on MS Windows O/S this is used for faster searching] feature for each system and user home drive(s).
4. For Linux/Unix mount points consider mounting them using "noatime".

3.17 Network Load Balancing Configuration

For AhsayOBS servers which are configured with network load balancing, i.e. a dual WAN router or Round Robin routing. A static route should be configured for your AhsayOBS server connection to the Ahsay license server (lic.ahsay.com). This will ensure the remote IP address sent by AhsayOBS to the Ahsay license server will remain the same during daily routine license checks. This will avoid potential license errors, i.e. 1011 or 1012 license errors which could result of the automatic shutdown of your AhsayOBS service.

3.18 AhsayOBS Reseller Panel and AhsayRDR

If you plan to use Reseller Panel feature on your AhsayOBS server(s), you will not be able to implement AhsayOBS in an AhsayRDR setup as this configuration is not supported in the current release.

4 Server Configuration

This chapter describes how you can use the [Manage System] -> [Server Configuration] page (shown below) to manage the configuration of your backup server.

System Settings

Login Name : system
 Password :
 Host Name : localhost
 System Home : C:\ProjectAhsay\obsr\cbase\system
 Policy Home : C:\ProjectAhsay\obsr\cbase\system\policy
 User Homes : 1. C:\ProjectAhsay\obsr\cbase\user
 Single Level Access : Limited system users and backup users access on current level and one below

Email System Settings

SMTP Server
 Host Name : 1. smtp.your-company.com
 Login Name :
 Password :
 Report Sender : Name: Backup Manager, Email: report@your-company.com
 Administrator Contact : Name: 1. System Admin, Email: admin@your-company.com
 Language of System Reports : English

Use Proxy

Type :
 Proxy Host : Port :
 Proxy Username : (optional)
 Proxy Password : (optional)

Edit [INSTALL_FOLDER] \ webapps \ ROOT \ lib \ common.js to customize your company logo and the names of softwares. After that, you can delete the content of "RenameProcedure" to remove this line.

Options

Use Windows Active Directory (AD) Authentication

Domain Name : *
 Domain Controller IP :
 Domain Controller Name : ins.ahsay.com
 Remove AhsayOBS Account : After a user account has been deleted from AD for 30 days, AhsayOBS will delete this user account automatically.
 After a user account has been disabled from AD for 30 days, AhsayOBS will delete this user account automatically.

Use Redirector (RDR)

Protocol : http
 Hostname : Port : 80
 Login Name :
 Password :

Language Settings

<input type="checkbox"/> Bulgarian	<input type="checkbox"/> Catalan	<input checked="" type="checkbox"/> Czech
<input type="checkbox"/> Danish	<input checked="" type="checkbox"/> German	<input checked="" type="checkbox"/> Greek Modern
<input checked="" type="checkbox"/> English	<input checked="" type="checkbox"/> Spanish	<input type="checkbox"/> Euskara
<input checked="" type="checkbox"/> Finnish	<input checked="" type="checkbox"/> French	<input type="checkbox"/> Hebrew
<input checked="" type="checkbox"/> Hungarian	<input checked="" type="checkbox"/> Icelandic	<input checked="" type="checkbox"/> Italian
<input checked="" type="checkbox"/> Japanese	<input type="checkbox"/> Korean	<input checked="" type="checkbox"/> Lithuanian
<input checked="" type="checkbox"/> Dutch	<input checked="" type="checkbox"/> Norwegian	<input type="checkbox"/> Polish
<input checked="" type="checkbox"/> Portuguese (Brazil)	<input checked="" type="checkbox"/> Portuguese (Portugal)	<input type="checkbox"/> Romanian
<input checked="" type="checkbox"/> Russian	<input checked="" type="checkbox"/> Slovenian	<input checked="" type="checkbox"/> Swedish
<input type="checkbox"/> Thai (Thai digits)	<input checked="" type="checkbox"/> Turkish	<input checked="" type="checkbox"/> Chinese (Simplified)
<input checked="" type="checkbox"/> Chinese (Traditional)		

Features Settings

Show Help link
 Show Restore Link
 Show FAQ link
 Show Install Link

Edit [INSTALL_FOLDER] \ webapps \ ROOT \ lib \ common.js to customize your company logo and the names of softwares. After that, you can delete the content of "RenameProcedure" to remove this line.

Key	Description
Login Name/Password	Username and password of the system account.
Host Name	A resolvable hostname of this server (e.g. backup.your-company.com). Although you can supply an IP address here, it is preferable to use a host name instead.
System Home	The directory where AhsayOBS stores its system information. The default directory for [System Home] is %OBSR_HOME%\system. Normally, you do not need to modify the value of this setting unless you want to store this information elsewhere.
Policy Home	The directory where AhsayOBS stores its system user and group policy information. The default directory for [Policy Home] is %OBSR_HOME%\system\policy. Normally you do not need to modify the value of this setting unless you want to store this information elsewhere.
User Homes	The directories where AhsayOBS store the backup files and backup log for all its users. You should set [User Homes] to partition where there is lots of free space.
Single Level Access	It determines whether system user has been restricted access to own created system users and backup users.
SMTP Server	The SMTP server that AhsayOBS will use to deliver its email reports.
Report Sender	The name of email address that will be used as a sender for all outgoing emails.
Administrative Contact	The name(s) and email address (es) of the system administrator. System reports (e.g. Daily Usage Report and Daily Error Report) will be delivered to these mailboxes.
Language of System Reports	The language which will be used in all system reports.
Use Proxy	Whether to use proxy to access the internet.
Type	The type of proxy to be used (HTTP / SOCKS).
Proxy Host/Port	Proxy server host and port number.


Proxy Username/Password	Proxy user name and password if user authentication is used.
Use Windows Active Directory (AD) Authentication	Whether to use Windows Active Directory Authentication.
Domain Name	The domain name to be used for AD authentication.
Domain Controller IP	The IP address of the domain controller.
Remove AhsayOBS account	Whether to delete AhsayOBS user account when AD user account is disabled/deleted.
Use Redirectory(RDR)	Whether to use redirector.
Protocol	The type of protocol to be used (HTTP/HTTPS)
Hostname/Port	Redirector host and port number.
Login Name/Password	System username and password for the redirector.
Use Windows Event Log	When this option is enabled, this backup server writes the system log message to Windows Event Log. This feature is only valid in Windows platform.
Language Setting	It determines whether different languages are enabled.
Feature Setting	It determines whether the [FAQ], [HELP], restore link and install link should be available to users.
Permission updated files	It determines whether the existing files are copied to retention area before updating the permission settings.
Moved Files	It determines whether the existing files are copied to retention area before updating the file paths.
Auto User Home Allocation	Maximum QPS Ratio can be changed.
Welcome Email	It determines if welcome email will be sent to new users and other options on welcome emails.
Enable Free Trial Registration	Whether to enable free trial user registration.
Backup Quota	The default backup quota of trial users

Add-on Modules	The default modules available to trial users
Remove User	Whether to remove trial users and the length of trial period.

4.1 User Languages Setting

The language of the web interface can be easily changed to another language by:

1. Click the [Select Language] link available on the top right hand corner of the web interface.
2. Select the language of your choice.
3. All text messages from the original window are now displayed in the language you have just selected (see example below).



Resum Usuari

No.	Grup de dades a copiar	Àrea de Dades**	Àrea de Retenció**	Càrrega Total*	Restauració Total*
1.	BackupSet-0	1.28M / 1.85M [31%] [161]	0 / 0 [0%] [0]	1.28M [161]	0 [0]
	Total	1.28M / 1.85M [31%] [161]	0 / 0 [0%] [0]	1.28M [161]	0 [0]

* Unitat : Mida Comprimida (Nombre Total d'Arxius)
** Unitat : Mida comprimida / Mida descomprimida [Ratio] [Nombre Total d'arxius]

Perfil d'Usuari : user

Directori Inicial : 0 (Project\Ahsay\obser\class\user\user)

Àlies : [input field]

Contrasenya : 4Grc0Um0Wau+VuBX8g+IPg== (No visible)
Nou [input field] (cancel·lar texte)

Espai Total : 50.0 [input field] kbytes mbytes gbytes

Ample de Banda : Ilimitada [dropdown] Bits/segon

Client de backup : Usuari AhsayOBM [dropdown]

Grup de publicitat assignat : No mostrar anuncis a aquest usuari
 Només els següents grups de publicitat:
 Grup de publicitat per defecte

Tipus : Usuari Actiu [dropdown] Usuari de pagament Suspès el 2016-01-01 (YYYY-MM-DD)

Estat : Actiu Suspès

Mòduls Addicionals : Microsoft Exchange Server Microsoft SQL Server
 Oracle Database Server Servidor de Base de Dades MySQL
 Lotus Domino Lotus Notes
 Deltas Volume Shadow Copy
 Bústia de Microsoft Exchange [input field] (Màx: 100)
 AhsayOBM JVM Royalty
 Delta Merge
 Continuous Data Protection ShadowProtect System Backup
 Microsoft Windows System Backup

Idioma : Anglès [dropdown]

Zona Horària : GMT+08:00 (CST) [dropdown]

The languages currently supported by AhsayOBS are listed in Appendix A. You can limit the list of languages available to users by using the [Manage System] -> [Server Configuration] -> [Language Setting] options.

If you uncheck all checkboxes for all languages available in [Manage System] -> [Server Configuration] -> [Language Setting], the [Select Language] will no longer be available on the top right hand corner of the web interface (you need to refresh the top menu bar to see the change). Users will not be able to change the language of the web interface.

Options

Language Settings :

- Bulgarian
- Catalan
- Czech
- Danish
- German
- Greek Modern
- English
- Spanish
- Euskara
- Finnish
- French
- Hebrew
- Hungarian
- Icelandic
- Italian
- Japanese
- Korean
- Lithuanian
- Dutch
- Norwegian
- Polish
- Portuguese (Brazil)
- Portuguese (Portugal)
- Romanian
- Russian
- Slovenian
- Swedish
- Thai (Thai digits)
- Turkish
- Chinese (Simplified)
- Chinese (Traditional)

Features Settings :

- Show Help link
- Show FAQ link
- Show Restore Link
- Show Install Link

Permission Updated Files : Keep a copy of all files with old permissions in the retention area

Moved Files : Keep a copy of all files under old file paths in the retention area

Auto User Home Allocation :

- User Home** : 1. C:\Program Files\AhsayObs60\user
- Current QPS Ratio** : 0.2% (50M / 20G)
- Maximum QPS Ratio** : Unlimited %

Welcome email : Send welcome email to new users Include encrypted password in welcome email


Enable Free Trial Registration

Backup Quota :

- 200 Mbytes [dropdown]
- Quota will be reset to 50 Mbytes after 0 Days
- User will be suspended after 90 Days

Add-on Modules :

- Microsoft Exchange Server
- Microsoft SQL Server
- MySQL Database Server
- Oracle Database Server
- Lotus Domino
- Lotus Notes
- In-File Delta
- Volume Shadow Copy



4.2 System Login Name/Password

The [Login Name] and [Password] setting under the [Manage System] -> [Server Configuration] page sets the login name and password (the default username is system password is system) that you would use to logon the system administration console. **Users are strongly recommended to change both the login name and password to something other than the default setting to reduce the possibility of unauthorized access to the AhsayOBS.**

4.3 Host Name

The [Host Name] setting under the [Manager System] -> [Server Configuration] page sets the hostname of the backup server. This entry will be used as a reference to the backup server in all email reports. Please enter a hostname/IP address (a public hostname/IP address if you expect backup request originating from the internet).

Please make sure the [Host Name] entry is resolvable from the backup server itself. This means that if you enter "backup.yourcompany.com" into the [Host Name] entry, you can access the backup system welcome page via http://backup.yourcompany.com.

If you are running AhsayOBS on custom TCP port (i.e. Not Port 80 and Port 443), please append your custom TCP port number to the [Host Name] entry. For example, if you are running AhsayOBS on TCP Port 8080 for HTTP, please enter "backup.your-backup.com:8080" as your [Host Name] entry (Please do

not enter the customer TCP Port for HTTPS, e.g. 8443, into the [Host Name] field as it will not work).

4.4 System Home, Policy Home and User Home Directories

The [System Home], [Policy Home] and [User Homes] setting under the [Manage System] -> [Server Configuration] page sets the system home directory, policy home directory and user home directories for AhsayOBS (the default values are %OBSR_HOME%\system, %OBSR_HOME%\system\policy and %OBSR_HOME%\user).

The system home directory for AhsayOBS defines a directory in which AhsayOBS will store all its system information.

The policy home directory for AhsayOBS defines a directory in which AhsayOBS will store all its system users and group policy information.

The user home directories for AhsayOBS define a list of directories in which AhsayOBS can be used to store the user folder for each backup user. Each user folder contains the backup setting as well as all backup data owned by this particular user.

AhsayOBS can be configured with multiple user home directories, this allows for the distribution of user accounts across different hard disk partitions or different hard disks. This enables server administrator's to easily distribute the I/O loading across multiple drives, which helps to improve overall backup server performance. Also, the support of multiple user homes will allow for easy expansion of the server storage. For example, if you want to add more storage to AhsayOBS, you can simply add another hard disk to the system and add the path to this new drive (e.g. E:\ or E:\Users) to the [User Homes] setting. You can then add new backup users or move existing backup users to this user home drive.

Backup users created by the AhsayOBM or AhsayACB "Free Trial Registration" wizard will always use the first [User Homes] entry as the user home to create backup users. If you want to offer free trial to your users and have enabled the "Free Trial Registration" option on the [Manage System] -> [Server Configuration] page, please make sure that there is enough free space available in the first entry of the [User Homes] settings to avoid running out of free space.

4.5 Single Level Access

The [Single Level Access] settings under the [Manage System] -> [Server Configuration] page defines system user access restriction to own created system users, backup users and backup users of system users. This restriction does not apply to system administrator. If you uncheck [Single Level Access] checkbox, system user can access all descendant system users and backup users.

4.6 Email System Setting

The [Email System Setting] settings under the [Manage System] -> [Server Configuration] page defines the various email setting that AhsayOBS will use to generate email reports to backup system administrator and backup users.

The [Email System Setting] -> [SMTP Server] -> [Host Name] entry defines the SMTP server that will be used by AhsayOBS to deliver its email reports. If you are using a SMTP server that is not running on SMTP standard TCP port (port25), please append your customer TCP port number for SMTP service to the [SMTP Server] -> [Host Name] entry (e.g. mail.your-company.com:8025).

You are only required to fill in the [SMTP Server] -> [Login Name] and [SMTP Server] -> [Password] entry if the SMTP server you are using required user authentication before accepting mail delivery requests.

Multiple SMTP servers can be setup for AhsayOBS. If the first SMTP server is unavailable, the next SMTP server will be used.

The [Email System Setting] -> [Report Sender] entry defines the "Mail-From" email address that appears in all outgoing emails generated by AhsayOBS.

The [Email System Setting] -> [Administrator Contact] entry defines the administrative contact of AhsayOBS. AhsayOBS will send daily usage and error report and all critical system alerts to all email addresses defined here.

4.7 Proxy Setting

The [User Proxy] settings under the [Manage System] -> [Server Configuration] page defines whether AhsayOBS should use a proxy to gain access to the internet.

Two types of proxy, HTTP/HTTPS and SOCKS 4/5, are supported. You can use the [Proxy Host] and [Port] entries to define the location of your proxy server. If the proxy server you are using requires user authentication, please use the [Proxy Username] and [Proxy Password] entries to set the username/password for your proxy server.

Note:

Please make sure there are no traffic restrictions on the proxy server, which could affect backup/restore performance.

4.8 Windows Active Directory (AD) Authentication Setting

When Windows Active Directory Authentication is enabled, user authentication will be dispatched to Windows Active Directory (AD) automatically if AhsayOBS fails to authenticate a user logon using its own records. This means that if an AD is presented in the network, it is only required to create a user account once in AD and the same user account can also be used in AhsayOBS, because AhsayOBS will create this user account automatically after authenticating this logon using AD. When this user logs on to AhsayOBS, AhsayOBS will use Free Trial Registration settings above (even if it is not enabled) as the template of user profile (i.e. backup quota and add-on modules settings, but not Microsoft Exchange Mailbox which will be disabled by default) to be created. The user account created will be of "Paid" type and of "AhsayACB" backup client (unless the user logs on using "AhsayOBM").

To enable this feature, simply check the box of [Use Windows Active Directory (AD) Authentication] under the [Manage System] -> [Server Configuration] page (by default it is enabled).

To synchronize AhsayOBS and AD, removal of users can be configured. If you want to delete/disable AhsayOBS user account when the user is removed from AD, you can check the boxes in the section of [Remove AhsayOBS Account]. You can have both options checked and create your own standard. For example, setting [After a user account has been deleted from AD for 20 days, AhsayOBS will delete this user account automatically] and [After a user account has been deleted from AD for 10 days, AhsayOBS will disable this user account automatically], can results that when the user account is removed from AD after 10 days, the user account will be disabled and after 10 more days, the user account will be deleted.

4.9 Redirector

The [Use Redirector (RDR)] settings under the [Manage System] -> [Server Configuration] page defines whether the current AhsayOBS is used behind a redirector. If AhsayOBS is a member machine of an AhsayRDR setup, you must specify the AhsayRDR settings

WARNING:


AhsayRDR does not support AhsayOBS member servers that are configured with Reseller Panel settings.

4.10 Language Setting

The [Language Setting] settings under the [Manage System] -> [Server Configuration] page defines the list of available languages on the web interface.

4.11 Features Setting

The [Feature Setting] settings under the [Manage System] -> [Server Configuration] page defines whether some customizable features on the web interface should be enabled or not.



Key	Description
Show FAQ link	It defines whether the [FAQs] link should appear at the top right hand corner of the web administration console (user interface only).
Show Help link	It defines whether the [Help] link should appear at the top right hand corner of the web administration console (user interface only).
Show Restore link	It defines whether the [Restore] link should appear at the top right hand corner of the web administration console (user interface only).
Show Install link	It defines whether the [Install Software] link should appear at the top right hand corner of the web administration console (user interface only).

4.12 Permission Updated Files

The [Permission Updated Files] settings under the [Manage System] -> [Server Configuration] page defines whether AhsayOBS should make a copy of the file to the retention area before the file permission changes. When this option is set, all backup accounts will use more retention space but allows the users to restore the same file with various permissions. When this option is not set, the permission changes are updated to the backup file directly. No copies of the previous version(s) will be available for restore.

4.13 Moved Files

The [Moved Files] settings under the [Manage System] -> [Server Configuration] page defines whether AhsayOBS should make a copy of the file to the retention area before the file path is updated, i.e. the files is moved to another location. When this option is set, all backup accounts will use more retention space but allows the users to restore the same file with the correct location. When this option is not set, the file path changes are updated to the backed up file directly. No copies of the previous version(s) will be available for restore.

4.14 Auto User Home Allocation

The [Auto User Home Allocation] settings under the [Manage System] -> [Server Configuration] page defines the quota ratio for each user home. AhsayOBS will automatically select the user home to be used for auto user allocation and trial user registration based on the quota ratio. AhsayOBS will always use the first user home with a QPS ratio smaller than the value defined by the system user.

4.15 Welcome Email

The [Send welcome email to new users] settings under the [Manage System] -> [Server Configuration] page defines whether AhsayOBS should send a welcome email to new users. If this option is checked, it will send an email to the new users.

The [Include encrypted password in welcome email] settings under the [Manage System] -> [Server Configuration] page defines whether AhsayOBS should include the encrypted password in the welcome email. When this option is checked, the encrypted password will send with the welcome email to the new users.

4.16 Free Trial Setting

The [Enable Free Trial Registration] settings under the [Manage System] -> [Server Configuration] page defines various free trial settings available in AhsayOBS.

Trial users do not count towards the maximum number of users allowed within AhsayOBS by the software license and there can be unlimited number of trial users within AhsayOBS. However, each backup user can have a maximum backup quota of 100GB for a trial period of 30 days. After expiration of the trial period, the backup quota will reset to a maximum of 500MB automatically.

To allow users to create a trial backup account from AhsayOBM or AhsayACB, please enable the [Enable Free Trial Registration] option. If this feature is unchecked, the option to register for a trial account (see below) will not be available to end users.



The screenshot shows the 'Trial Registration' dialog box with the 'Proxy Setting' section expanded. The 'Language' is set to 'English'. The 'Backup Server' section shows a protocol dropdown set to 'http' and an empty address field. The 'Proxy Setting' section has a checkbox for 'Use proxy to access the backup server' which is unchecked. Below it, there are radio buttons for 'Proxy' (selected) and 'Sock'. There are also input fields for 'Address', 'Port', 'User Name', and 'Password'. At the bottom, there are 'Next' and 'Cancel' buttons.



The screenshot shows the 'Trial Registration' dialog box with the 'User Information' section expanded. The 'Language' is set to 'English'. The 'User Information' section has input fields for 'Login Name', 'Password', and 'Confirm Password'. Below it is a 'Contact' section with an 'Email' input field. A note at the bottom states '*ALL fields are required'. At the bottom left, there is a link 'Already a user?' and at the bottom right, there are 'Submit' and 'Cancel' buttons.

The [Backup Quota] defines the maximum backup quota of trial backup accounts upon registration.

The [Add-on Modules] option defines whether you want to allow trial users to have different add-on modules.

The [Remove User] option defines whether you want to remove trial backup users for certain number of days after registration. For example, you can use

this option to tell AhsayOBS to remove trial backup users from the system automatically after backup users have registered for 60 days.

4.17 Use Windows Event Log

For AhsayOBS installations on Microsoft Windows platform which have the "Windows Event Log" service enabled. When this feature is selected all AhsayOBS system log information, i.e. error, warning, and information message types will be also be written to the Windows event logs. The backup server administrator's can view the logs entires using the Windows event viewer. The event log name is limited to 8 characters.

After a user account has been disabled from AD for days, AhsayOBS will delete this user account automatically.

Use Redirector (RDR)

Protocol :

Hostname : Port :

Login Name :

Password :

Use Windows Event Log

Event Log Name :

Options

Language Settings

<input checked="" type="checkbox"/> Bulgarian	<input checked="" type="checkbox"/> Catalan	<input checked="" type="checkbox"/> Czech
<input checked="" type="checkbox"/> Danish	<input checked="" type="checkbox"/> German	<input checked="" type="checkbox"/> Greek Modern
<input checked="" type="checkbox"/> English	<input checked="" type="checkbox"/> Spanish	<input checked="" type="checkbox"/> Basque
<input checked="" type="checkbox"/> Finnish	<input checked="" type="checkbox"/> French	<input type="checkbox"/> Hebrew
<input checked="" type="checkbox"/> Hungarian	<input checked="" type="checkbox"/> Icelandic	<input checked="" type="checkbox"/> Italian
<input checked="" type="checkbox"/> Japanese	<input checked="" type="checkbox"/> Korean	<input checked="" type="checkbox"/> Lithuanian
<input checked="" type="checkbox"/> Dutch	<input checked="" type="checkbox"/> Norwegian	<input checked="" type="checkbox"/> Polish
<input checked="" type="checkbox"/> Portuguese (Brazil)	<input checked="" type="checkbox"/> Portuguese (Portugal)	<input checked="" type="checkbox"/> Romanian
<input checked="" type="checkbox"/> Russian	<input checked="" type="checkbox"/> Slovenian	<input checked="" type="checkbox"/> Swedish
<input checked="" type="checkbox"/> Thai (Thai digits)	<input checked="" type="checkbox"/> Turkish	<input type="checkbox"/> Ukrainian
<input checked="" type="checkbox"/> Chinese (Simplified)	<input checked="" type="checkbox"/> Chinese (Traditional)	

The ID for each message type is shown in the following table.

Type	ID
Information	201
Warning	305
Error	409

5 Software License

This chapter describes how you can use the [Manage System] -> [Software License] page (shown below) to manage software license of AhsayOBS.

License Setting

Licensee Name : EvaluationOnly

License Key : f2pMG-YPD6l-3ggaG-b5MCT-xA

Contact

Company Name :

Contact Name :

Contact Email Address :

Contact Phone Number :

Number of users	Quota	Used	Available
AhsayOBM	10	3	7
AhsayACB	10	0	10

User Add-on Modules	Quota	Used	Available
Microsoft Exchange Server	10	1	9
Microsoft Exchange Mailbox	10	0	10
Microsoft SQL Server	10	1	9
Oracle Database Server	10	1	9
MySQL Database Server	Unlimited		
Lotus Domino	10	1	9
Lotus Notes	10	1	9
In-File Delta	10	2	8
Volume Shadow Copy	10	2	8
AhsayOBM JVM Royalty	10	1	9

Volume Shadow Copy	10	2	8
AhsayOBM JVM Royalty	10	1	9
Delta Merge	10	0	10

Server Add-on Modules

AhsayOBS Replication Module : Enable

AhsayOBS JVM Royalty : Enable

Details

Product Name : Ahsay Online Backup Software, Standard Evaluation Edition

Product Version : 6.0.0.0

Expiry Date : 2008/09/26

Free Upgrade Until : 2009/05/03

Max Quota : Unlimited

Key :

Licensee Name	Licensee of this product
License Key	License key to activate this product
Product Name	Product name
Microsoft SQL Server	Module for backing up Microsoft SQL Server
Oracle Database Server	Module for backing up Oracle Database Server
Lotus Domino	Module for backing up Lotus Domino Server
Lotus Notes	Module for backing up Lotus Notes Client
Microsoft Exchange Server	Module for backing up Microsoft Exchange Server
MySQL Database Server	Module for backing up MySQL Database Server
AhsayOBS Replication Module	Module for replicating AhsayOBS to another server
In-File Delta	Module for backing up file using In-File Delta
Volume Shadow Copy	Module for backing up file using volume shadow copy
Microsoft Exchange Mailbox	Module for backing up Microsoft Exchange individual emails
Product Version	Product version

Key	Description
License Name	Business name of the licensee
License Key	License Key to activate this software. Please enter [License Key] as a printed on the [Software License Agreement] into the text field provided.
Company Name	The company name used for contact.
Contact Name	The name of the contact person.
Contact Email	The email address of the contact person.
Contact Number	The phone number of the contact person.
AhsayOBM	The maximum number of the AhsayOBM backup account allowed.
AhsayACB	The maximum number of the AhsayACB backup accounts allowed.
User Add-on Modules	<p>It shows whether different client side add-on modules are enabled for AhsayOBM/AhsayACB. You need to have a new license key to enable these modules.</p> <p>Quota – the total number of licenses of a particular module available.</p> <p>Used – the total number of licenses of a particular module assigned to users.</p> <p>Available – the total number of license of a particular module available for future use.</p>
Server Add-on Modules	It shows whether different server side add-on modules are enabled for AhsayOBS/AhsayRPS. You need to have a new license key to enable these modules.
Product Name	Name of the licensed product.
Product Version	Version number of the licensed product.
Expiry Date	The date when the current license key will expire. You will not be able to use AhsayOBS after this date.
Free Upgrade Until	The last date you are allowed to upgrade to the latest AhsayOBS available. You will not be able to upgrade to any software release after this date with your current license key.

Max Quota	The maximum quota for each backup user supported.
-----------	---

5.1 Licensee Name and License Key

When you click the [Manage System] -> [Software License] link available at the top menu, the [Software License] panel will appear (see above). You can use the form available on this panel to activate the software.

Please remember the following notes when you enter your licensee name and your license key:

- Both [Licensee Name] and [License Key] are case sensitive and they must be entered EXACTLY as stated in your software receipt. If possible, please use copy and paste shortcuts (CTRL-C and CTRL-V) to enter both the [Licensee Name] and [License Key] into the field provided to avoid typo error.
- If a proxy server is required to access the Internet from AhsayOBS, please setup the [proxy setting] in the [Manager Server] page. Access to the Internet is required because the license key must be activated by our license server before it is usable.
- If internet connection is not available in your environment, you can use the offline activation method to activate your license.
- One license key can only be used on one machine once it has been activated. If you use the same license key to activate another copy of AhsayOBS on another server, you will get an "Internal Error 1011" or "Internal Error 1012" message. You can still run this copy of AhsayOBS for another 7 days without any problems but it will stop working after this grace period. Please contact us to re-activate your license key if you run into this situation.


5.2 Automatic License Renewal

If AhsayOBS is under a monthly leasing plan, the license key will have an expiry date of 30 days. Upon expiration, the license key will be renewed automatically.

In the event of any problems during the license renewal process, i.e. AhsayOBS is not able to connect to the Ahsay License server. The expired license key will have a grace period of 14 days. AhsayOBS can still function normally using the expired license for an extra 14 days before the service is automatically shutdown. The 14 day grace period is to allow sufficient time to resolve any license related problems.

5.3 Evaluation Expiry and Free Edition

After the evaluation period, the evaluation key will expire and the AhsayOBS will automatically be stopped. Although the service will still be alive, AhsayOBM and AhsayACB cannot do backups anymore. You should get the following screen when it happens:



If you want to continue using AhsayOBS, you can press the [Buy Licenses Online] button to purchase new licenses or contact our Sales Team https://kb.ahsay.com/index.php?_m=tickets&_a=submit

However, if you have not yet decided to purchase our product, you are welcome to apply for a free license. To apply for a free license, please input all contact details (including [Company Name], [Contact Name], [Contact Email Address], [Contact Phone Number]), and then press the [Request for free license] button. An email will be sent to your email account in a short time.

[Standard Evaluation License.checkLicTime] License expired on 2008-07-26. Server is stopped.

A Free License key is sent to the contact email address. Please fill in that license key and click "update" button.

Request for free license | Buy Licenses Online!

License Setting

Licensee Name : EvaluationOnly

License Key : 62pMG-YPD6l-3ggaG-b5MCT-xA

Contact

Company Name : your-company

Contact Name : your-name

Contact Email Address : your-email@your-company.com

Contact Phone Number : (country-code) your-number

Number of users	Quota	Used	Available
AhsayOBM	10	2	8
AhsayACB	10	0	10

User Add-on Modules	Quota	Used	Available
Microsoft Exchange Server	10	0	10
Microsoft Exchange Mailbox	10	0	10
Microsoft SQL Server	10	0	10
Oracle Database Server	10	0	10
MySQL Database Server	Unlimited		

Your Company Logo

Within the email, you will have the licensee name and license key received. Copy and paste the values to the fields on the page of [Manage System] -> [Software License] respectively. After that, press the [Update] button at the end of the page. Then you should be able to continue to use AhsayOBS.

If you have created some backup users in AhsayOBS before, you may get the following message on the license page:

Quota is exceeded. Some users are suspended due to out of quota.

License Setting

Licensee Name : FREE_your-email@your-company.com99

License Key : XXXXXXXXXXXXXXXXXXXX

Contact

Company Name : your-company

Contact Name : your-name

Contact Email Address : your-email@your-company.com

Contact Phone Number : (country-code) your-number

Number of users	Quota	Used	Available
AhsayOBM	0	0	0
AhsayACB	2	0	2

User Add-on Modules	Quota	Used	Available
Microsoft Exchange Server	0	0	0
Microsoft Exchange Mailbox	0	0	0
Microsoft SQL Server	0	0	0
Oracle Database Server	0	0	0
MySQL Database Server	Unlimited		
Lotus Domino	0	0	0
Lotus Notes	0	0	0
In-File Delta	2	1	1
Volume Shadow Copy	2	1	1

Your Company Logo

The system prompts that the quota is exceeded, because generally free version of AhsayOBS has more limitations on number of users, modules and features than evaluation version. When it changes to Free Edition, the extra users will be suspended and the user accounts will stop functioning. Users to be suspended are chosen randomly. We would recommend that you should remove/suspend the extra users before switching to Free Edition.

After you have purchased a new license, you can apply the licensee name and license key as described in previous sections. You can then re-activate the users by using the tools in [Manage User]. For more information on [Managing User], please refer to the section of Managing User in this document.

5.4 Offline License Activation

Offline License Activation is a new feature added to AhsayOBS since v5.5.7.0. It is used to activate the AhsayOBS license for servers that do not have internet connection.

In order to use the offline license activation, you must first install AhsayOBS v5.5.7.0 or above.

After you have finished installing the AhsayOBS, please open the web management console and go to the license page ([Manage System] -> [Software License]). On that page, you should be able to see the [Advanced Option] link near the bottom right hand corner. Please click on that link to display the offline license options.

[Manage System](#) | [Manage Log](#) | [Manage User](#) [Administrator's Guide](#) | [Select Language](#)
[Server Configuration](#) | [Routine Job](#) | **[Software License](#)** | [Replication Config](#) | [Other Options](#) [Logout](#)


License Settings			
License Name	:	<input type="text" value="911"/>	
License Key	:	<input type="text" value="wg8U7-S4bDz-Gc/co-YjTqm-qQ"/>	
Contact			
Company Name	:	<input type="text" value="Ahsay Testing"/>	
Contact Name	:	<input type="text" value="Lic Test"/>	
Contact Email Address	:	<input type="text" value="jo.kwok@ahsay.com"/>	
Contact Phone Number	:	<input type="text" value="11223344"/>	
Number of users	Quota	Used	Available
AhsayOBM	: 40	3	37
AhsayACB	: 35	0	35
User Add-on Modules	Quota	Used	Available
Microsoft Exchange Server	: 35	2	33
Microsoft Exchange Mailbox	: 25	0	25
Microsoft SQL Server	: 35	2	33
Oracle Database Server	: 35	2	33
MySQL Database Server	: Unlimited		
Lotus Domino	: 35	2	33
Lotus Notes	: 35	2	33
In-File Delta	: 35	2	33
Volume Shadow Copy	: 35	2	33
AhsayOBM JVM Royalty	: 35	2	33
Server Add-on Modules			
AhsayOBS Replication Module	:	Enable	
AhsayOBS JVM Royalty	:	Enable	
Details			
Product Name	:	Offsite Backup Software, OEM Edition	
Product Version	:	5.5.5.4-3	
Expiry Date	:	2011/01/13	
Free Upgrade Until	:	2010/09/02	
Max Quota	:	Unlimited	

Click here show off-line license option

[Advanced Options](#)

The offline license options should now be shown on the screen. The next step in the offline license activation process is to generate an offline license request file. This file is an encrypted file that contains all the information required for the activation process, e.g. MAC address and local IP address. To generate the offline license request file, please press the [Generate] button under the [Advanced Option] under of the license page. The offline license

request file will then be generated and it will prompt for the location to save the offline license request file.



When the offline license request file is ready, please send it to our Support team via email. An offline license file will then be generated and sent back to you. The offline license file is the license file used in the offline license activation process.


After you have received the offline license file, you would need to import it to the AhsayOBS to complete the offline activation process. Before importing the offline license files to AhsayOBS, you must ensure that it is placed in the system home folder of AhsayOBS. Then, you should logon to the AhsayOBS web interface to import the license from the [Software License] page (i.e. [Manage System] -> [Software License]) and click on the [Advanced Option] link. Press on the [Browse] button and select the offline license file from AhsayOBS system home. Click on the [Offline Update] button to complete the process. If there is no error message shown on the [Software License] page, the Offline License Activation process is completed successfully.

5.5 License Management Portal

The [License Management Portal](#) is an online license management tool. It provides a convenient method for partners to manage their AhsayOBS license keys online. For more information on this feature, please refer to the online documentation on the License Management Portal.

6 Managing Routine Job

This chapter describes how you can use the [Manage System] -> [Routine Job] page (shown below) to manage number of system routine jobs of AhsayOBS. When you click the [Manage System] -> [Routine Jobs] link available at the top menu, the [Routine Jobs] panel will appear. You can use the form available on this panel to define your preferences of how you want different system routine jobs to run.



Key	Description
Backup Report	Hourly job sending backup reports to users whose backup job have completed within the last hour.
Online Restore Report	Hourly job sending online file restoration reports to users who have performed and completed an online file restoration action within the last hour.
Setting Change Report	Hourly job sending setting change reports to users who have updated their backup setting within the last hour.
Missed Backup Report	Hourly job checking whether any scheduled backup job has been missed for all backup users and sending missed backup reports to users who have missed their backup jobs.
Inactive User Report	Daily job sending inactive user reports to users if their accounts have been inactive for more than 7 days.

Off-line Backup Reminder	Daily job sending off-line backup reminders to users who have set the off-line backup option and have not performed a backup for the required number of days.
Backup Quota Reminder	Daily job sending backup quota reminders to users whose storage quotas are above a certain percentage.
Trial user Reminder	Daily job sending trial user reminders to users whose trial account are about to expire.
Usage Report	Daily job sending system usage reports to system administrators.
Error Report	Daily job sending system error reports to system administrators.
Replication Error Report	Daily job sending replication error reports to system administrators
Inactive User Removal	Daily job deleting all trial accounts that have been inactive for 60 days.
Retention Policy Job	Daily job removing obsolete files from the retention area according to each user's retention policy setting.
Rebuild User Storage	Weekly job rebuilding all users' storage information by walking through all users' backup files.
System Log Removal	Daily job removing system logs older than this number of days from the system.
Debug Log Removal	Daily job removing debugging logs older than this number of days from the system.
Cyclic Redundancy Check (CRC) Checking	Routine job that will run at 2 nd and 4 th Saturdays of every month. It will verify the CRC of the files backed up to the server.
Force to check all backup files	If selected the CRC job will check all backup files regardless of last checked date.

Note:

It is strongly recommended you enable the CRC checking so that regular file integrity checks are made on the backup data files.

6.1 Backup Report

The [User Report] -> [Backup Report] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Backup Report] routine job. The role of the [Backup Report] routine job is to send backup reports to users who have finished one of their backup jobs within the last hour. The backup report is scheduled to run every 57 minutes past the hour.

If you want your users to receive these reports, please select the [Enable] option. Otherwise, select the [Disable] option.

6.2 Online Restore Report

The [User Report] -> [Online Restore Report] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Online Restore Report] routine job. The role of the [Online Restore Report] routine job is to send online file restoration reports out to users who have performed and completed an online file restoration action within the last hour. The online restore report is scheduled to run every 58 minutes past the hour.

If you want your users to receive these reports, please select the [Enable] option. Otherwise, select the [Disable] option.

6.3 Setting Change Report

The [User Report] -> [Setting Change Report] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Setting Change Report] routine job. The role of the [Setting Change Report] routine job is to send reports out to users who have updated their profiles or backup set within the last hour. The setting change report is scheduled to run every 59 minutes past the hour.

If you want your users to receive these reports, please select the [Enable] option. Otherwise, select the [Disable] option.

6.4 Missed Backup Report

The [User Report] -> [Missed Backup Report] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Missed Backup Report] routine job. The role of the [Missed Backup Report] routine job is to send reminder notice to users who have missed one of their scheduled backup jobs. AhsayOBS defines a scheduled backup job to be a missed backup job if there is no backup run 6 hours after a backup has been scheduled. The missed report is scheduled to run every 56 minutes past the hour.

If you want your users to receive these reports, please select the [Enable] option. Otherwise, select the [Disable] option.

6.5 Inactive User Report

The [User Report] -> [Inactive User Report] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Inactive User Report] routine job. The role of the [Inactive User Report] routine job is to send a reminder notice to users who have been inactive on the system.

This job will run daily as defined by the [Daily at] setting, the default start time is 09:20 AM. If you want your users to receive these reports, please select the [Enable] option. Otherwise, select the [Disable] option.

6.6 Off-line Backup Reminder

The [User Report] -> [Off-line Backup Reminder] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Off-line Backup Reminder] routine job. The role of the [Off-line Backup Reminder] routine job is to send a reminder notice to users who have set the off-line backup option in their backup sets but failed to backup for a certain amount of time.

This job will run daily as defined by the [Daily at] setting, the default start time is 09:25 AM. If you want your users to receive these reports, please select the [Enable] option. Otherwise, select the [Disable] option.

6.7 Backup Quota Reminder

The [User Report] -> [Backup Quota Reminder] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Backup Quota Reminder] routine job. The role of the [Backup Quota Reminder] routine job is to send a reminder notice to users whose storage quota usage has hit a pre-defined percentage, the default quota usage setting is more than 90%.

This job will run daily as defined by the [Daily at] setting, the default start time is 09:05 AM. If you want your users to receive these reports, please select the [Enable] option. Otherwise, select the [Disable] option. Please also set the pre-defined percentage of storage divided by quota that will trigger this reminder.

6.8 Trial User Reminder

The [User Report] -> [Trial User Reminder] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Trial User Reminder] routine job. The role of the [Trial User Reminder] routine job is to send a reminder notice to users whose trial accounts that their account will expire. The default setting is to send reminder reports 25 days after trial account registration.

This job will run daily as defined by the [Daily at] setting, the default start time is 09:50 AM. If you want your users to receive these reports, please

select the [Enable] option. Otherwise, select the [Disable] option. Please also set the number of days after registration that the users should get this reminder.

6.9 Usage Report

The [System Report] -> [Usage Report] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Usage Report] routine job. The role of the [Usage Report] routine job is to send usage report, which contains a statistics of all backup users' activities, to the administrative contacts of AhsayOBS.

This job will run daily as defined by the [Daily at] setting, the default start time is 09:55 AM. If you want the administrative contacts of AhsayOBS to receive the usage report, please select the [Enable] option. Otherwise, select the [Disable] option.

6.10 Error Report

The [System Report] -> [Error Report] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Error Report] routine job. The role of the [Error Report] routine job is to send error report, which contains a full listing of all system and backup errors, to the administrative contacts of AhsayOBS.

This job will run daily as defined by the [Daily at] setting, the default start time is 09:15 AM. If you want the administrative contacts of AhsayOBS to receive the error report, please select the [Enable] option. Otherwise, select the [Disable] option.

6.11 Replication Error Report

The [System Job] -> [Replication Error Report] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Replication Error Report] routine job. The role of the [Replication Error Report] routine job is to send the replication error report, which contains the list of errors appear during the replication process.

This job will run daily as defined by the [Daily at] setting, the default start time is 00:00 AM. If replication is enabled on AhsayOBS and you want the administrative contacts of AhsayOBS to receive the replication error report, please select the [Enable] option. Otherwise, select the [Disable] option.

6.12 Inactive User Removal

The [System Job] -> [Inactive User Removal] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Inactive User Removal] routine job. The role of the [Inactive user Removal routine job is to

remove inactive trial users (i.e. no logon or backup traffic from this user) from AhsayOBS as defined by the Free Trial Setting.

This job will run daily as defined by the [Daily at] setting, the default start time is 09:35 AM. If you want this job to run, please select the [Enable] option. Otherwise, select the [Disable] option.

6.13 Retention Policy

The [System Job] -> [Retention Policy] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Retention Policy] routine job. The role of the [Retention Policy] routine job is to delete files from the retention area for each user according to the retention policy of each backup set of each backup user.

This job will run daily as defined by the [Daily at] setting, the default start time is 09:40 AM. If you want this job to run, please select the [Enable] option. Otherwise, select the [Disable] option.

WARNING:

Disabling the Retention Policy job could result in:

- i. user accounts exceeding their quota limits and therefore interrupting normal backup operations.**
- ii. AhsayOBS user home(s) drives running out of space, which could result in your AhsayOBS becoming unstable and or cause data corruption.**

6.14 Rebuild User Storage

The [System Job] -> [Rebuild User Storage] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Rebuild User Storage] routine job. The role of the [Rebuild User Storage] routine job is to recalculate all users' storage information (e.g. data area file size/number, retention area file size/number) by traversing through all backup files for all users within the system.

The job is designed to run weekly and will run at the time defined by the [Every WEEKDAY at] setting, the default start time is every Sunday at 09:30 AM. If you want this job to run, please select the [Enable] option. Otherwise, select the [Disable] option.

Note:

- i. **As the Rebuild User Storage job is relatively I/O intensive job, it is recommended to schedule this job to run during off peak periods.**
- ii. **When a rebuild user storage is run on a user account with active backupsets, the calculations for the storages statistics may not reflect the actual storage used as all active backupsets are skipped.**

6.15 System Log Removal

The [System Job] -> [System Log Removal] setting under the [Manage System] -> [Routine Job] page defines the setting of the [System Log Removal] routine job. The role of the [System Log Removal] routine job is to remove all system logs (i.e. all information under the System Home, e.g. system error logs or backup error logs) from AhsayOBS after the [Keep Logs For] number of days.

This job is designed to run daily and will run at the time defined by the [Daily at] setting, the default start time is 09:45 AM. If you want this job to run, please select the [Enable] option. Otherwise, select the [Disable] option.

6.16 Debug Log Removal

The [System Job] -> [Debug Log Removal] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Debug Log Removal] routine job. The role of the [Debug Log Removal] routine job is to remove all debugging logs (e.g. access logs and web application context logs) from AhsayOBS after the [Keep Logs for] number of days.

This job is designed to run daily and will run at the time defined by the [Daily at] setting, the default start time is 09:10 AM. If you want this job to run, please select the [Enable] option. Otherwise, select the [Disable] option.

6.17 Cyclic Redundancy Check (CRC) Checking

The [System Job] -> [Cyclic Redundancy Check (CRC) Checking] setting under the [Manage System] -> [Routine Job] page defines the setting of the [Cyclic Redundancy Check (CRC) Checking] routine job.

The role of this routine job is to check the CRC of the backup files on every 2nd and 4th Saturdays every month, the default start time is 12:00 AM.

The "Cyclic Redundancy Check (CRC) Checking" job will check all new files on AhsayOBS. When the CRC job checks a file it will update the file header with an 'AhsayOBS CRC next check date'. This is calculated as 180 + (random

number of 0 to 60) days, so for existing files which have been checked previously. The next CRC check on the file will be performed after 180 to 240 days.

During this checking, it will check the followings things:

- The file size of the backup file with the size stored in the header of backup file.
- The CRC value of the backup file with the checksum value stored in the header of the backup file.

If a file is found to be invalid or corrupted it will be deleted, if the file is in the retention area or retained if the file is in the "Current" folder.

To configure the "Cyclic Redundancy Check (CRC) Checking" job to validate all files regardless of the last checked date, please check the [Force to check all backup files] option.

WARNING:

Using the [Force to check all backup files] option could result in performance issues with your AhsayOBS server. This option may impact on backup and restore performance.

7 Managing Replication

The replication module is managed by the [Manage System] -> [Replication Config] page. For more information about this feature, please refer to the [Ahsay Replication Server Administrator's Guide](#).

Also, please refer to the [AhsayOBS and AhsayRPS Setup Guide](#) for information on how to install the AhsayRPS to work with AhsayOBS.

8 Managing Other Options

This chapter describes how you can use the [Manage System] -> [Other options] page (shown below) to manage the advertisements for all users and default In-File delta setting for AhsayACB users.



Key	Description
In-file delta setting	Select this option to enable and use in-file delta technology for all AhsayACB clients.
Block Size	The in-file delta block size used to detect changes within a file. A smaller block size should produce a smaller delta file but requires more processing power. The default setting of [Auto] will choose the optimal block size for each file based on the file's original file size.
Minimum Size	The minimum size setting defines the smallest file size to apply the in-file delta.
Delta Merge	To enable delta merging on all users.
In-File Delta Type	The In-File delta type to use for calculating the delta file: <ul style="list-style-type: none"> Incremental – this option uses the previous uploaded full or incremental file to calculate the delta. It produces the smallest delta for upload but requires the most time and processor power to restore. Differential – this option always uses the latest uploaded full file to calculate the delta. It

	<p>produces a larger delta but allows for the fastest restore.</p> <ul style="list-style-type: none"> •
Upload Full File	<p>The upload full file setting determines when the full file should be uploaded to the server instead of the delta. It depends on either of the following rules being true:</p> <ul style="list-style-type: none"> • Maximum No. of Delta – the total number of deltas uploaded since the last full file. The default setting is 100 deltas. • Delta Ratio – the ratio of the Delta Size divided by the Full file size. The default setting is 50%.
Adgroup for all AhsayACB and AhsayOBM users	<p>An adgroup groups multiple advertisements into a logical unit which can then be assigned to different users. All advertisements within an adgroup will be presented to all users who have been assigned to this adgroup.</p>
Advertisements	<p>Click the [Add] link to add new advertisements.</p>

8.1 In-File Delta Settings for all AhsayACB users

The [In-File delta settings for all AhsayACB users] setting under the [Manage System] -> [Other Options] page defines a global setting of In-File Delta Technology for all AhsayACB clients. Select this option to enable In-File Delta Technology for AhsayACB clients.

8.2 Block Size

The [Block Size] setting defines the size of data block being used to detect changes between the last full backup file and the file being backed up. In general, the smaller the block size, the more likely a matched data block can be found, hence produces a smaller delta file but will require more processing power to detect these changes. On the other hand, In-File delta backup running with a larger block size will run faster but this will generally produce a larger delta file.

The default setting [Auto] will select the optimal block size for each file depending on the size of the file. The [Auto] setting will set the block size according the following criteria:

File Size	Block Size
< 2 GB	4 KB
2 GB to 8 GB	8 KB
> 8 GB	16 KB

8.3 Minimum Size

The [Minimum Size] setting defines the smallest file size a file (the default value is 25 MB) must have before the use and application of in-file delta backup technology.

If the size of a file being backed up is smaller than the [Minimum File Size] setting, in-file delta backup technology won't be applied to this file and the whole file, instead of just the delta file, will be uploaded to the backup server. For backupsets which contain relatively small files, the [Minimum Size] should be increased. As it is not necessary to perform in-file delta backup on small files because backing up the full file doesn't take too long anyway. The advantage of backing up the full file is it will reduce the amount of time required to restore, i.e. the restore of one small full file is much quicker than the restore a small file with associated incremental delta's.

8.4 Delta Merge

The [Delta Merge] setting under the [Manage System] -> [Other Options] page defines a global setting of delta merging for all AhsayACB clients.

Once the "enable delta merge" option is selected:

- i. The in-file delta type will be automatically set to "incremental".
- ii. Delta merge will ignore the "Upload Full File" in-file delta settings.

8.5 In-File Delta Type

The [In-file Delta Type] setting defines the way In-File Delta files are handled. There are two different versions as follows:

Incremental In-File Delta

All delta files are generated with respect to changes made since the last incremental backup. This means that the last full backup file and all related incremental delta backup files are required to restore the latest snapshot of a backup file.

The full backup file, its checksum file and all incremental delta files are always stored in the data area. This means that these files are not affected by the setting of the retention policy and will always be kept on the backup server. But for backupsets with delta merge enabled, the retention policy setting is also used by the delta merge feature to determine when AhsayOBS will merge the full and incremental delta files into a new full file.

Differential In-File Delta

All differential delta files are generated with respect to changes made since the last full backup file. This means that only the last full backup file and the last differential delta file are required to restore the latest snapshot of a

backup file. The other intermediate differential delta files are only required if you want to restore intermediate snapshots of a backup file.

The advantage of a differential In-File delta backup is that a corrupted differential delta file would only make one particular snapshot of a backup file non-recoverable. All other snapshots can still be recovered using the remaining differential delta files.

The full backup file, its checksum file and the last delta file uploaded (if more than one delta files have been uploaded to the backup server) is always stored in the data area. This means that these files are not affected by the setting of the retention policy and will always be kept on the backup server. It is done this way because all these files are required to get the latest snapshot of the backup file and they should not be removed from the backup server by the retention area cleanup routine. All other intermediate delta files are stored in the retention area.

8.6 Upload Full File

The [Upload Full File] setting defines when to upload a full file instead of a delta file.

No. of Delta

The [No. of delta] setting defines the maximum number of delta files from the same full backup file to be generated and backed up to the backup server before a full backup (the whole file) of this file is uploaded to the backup server instead.

For example, if you have created 100 delta files from the full backup file already and this [No. of delta] setting is set at 100, the next backup will upload a full backup file (the whole file) instead of just the delta file. However, if the [No. of delta] setting is set to unlimited. It will keep generating delta files and uploading these delta files to the backup server until the other delta setting condition (delta ratio exceeded) forces a full backup. This setting is here to make sure that there will always be a full backup file after a certain number of delta files have been generated.

Delta Ratio

The [Delta Ratio] setting is defined as the file size of a delta file (the file size of the delta file generated by AhsayOBM on the client computer) and divided by the file size of its full backup file (the file size of the backup file on the disk of client computer), i.e. the percentage of changes detected between the last full backup file and the current file.

If the delta ratio calculated from the size of the generated delta file and the size of the full backup is greater than the [Delta Ratio] setting, the whole file, instead of just the delta file, will be backed up to the backup server. It is

done this way because the difference between backing up the whole file and the delta file is not significant and it is better to upload the whole file instead.

The default setting of [Delta Ratio] is 50%. This means that if the changes detected within a file are more than 50%, the whole file, instead of the delta file will be backed up and uploaded to the backup server.

It is recommended for backupsets where the full file size(s) are relatively small:

1. The [No. of delta] settings be kept to a low value
2. The [Delta Ratio] setting should be less than 50%
3. The [Minimum Size] setting should be increased to more than 25 MB

This will minimize the probability of future restore problems caused by invalid or corrupted delta files.

8.7 Adgroups

An adgroup groups multiple advertisements into a logical unit which can then be assigned to different users. All advertisements within an adgroup will be presented to all users who have been assigned to this adgroup.

To add a new adgroup, type the name of the adgroup in the empty field located under [Adgroup for all AhsayACB and AhsayOBM users] and next to the [New] text. Press the [Update] button at the bottom and a new adgroup will be created.

8.8 Advertisements


The [Advertisements] setting defines the advertisements and related information that is displayed at the bottom of all AhsayACB clients.

Key	Description
Add	Click this link to add a new advert.
Show Advertisement Log	Click this link to view the advertisement log.
Name	The name of the advertisement. Click the link to edit this ad.
Text	The text to be displayed at the bottom of the AhsayOBM/AhsayACB client.
Start Date	The data when this ad was created.
Popularity	Calculated value to indicate which ad. Is the most popular. The value is calculated as the percentage of

	[Hit for this ad.] divided by [Total Hits].
Hits	The "Hits" counter indicates the number of times this ad. has been clicked. These counters are only updated if the option "Enable Tracking" is set. The three values are [Hits within 1 day] / [Hits within the last 7 days] / [Hits within the last 30 days].
Time	The number of seconds to display the ad.
Move	The display sequence of the adverts.
Target	Click this link to test the advertisement's URL. This will open a browser and displays the URL web page.
Remove	Click this link to delete the ad.

Add New Advertisement

Click the [Add] link to add new advertisements. Enter the ad. information into the form provided.



Key	Description
Name	The name of the advertisement.
Assigned Adgroups	It determines if the advertisement should be included in the adgroup(s).
GIF Image	The full pathname of the image file to be displayed at the bottom of the AhsayOBM / AhsayACB client. The image size should be 468 x 60, and the format should be in GIF.
Flash Image	The full pathname of the flash image file to be displayed at the bottom of the AhsayOBM / AhsayACB client. The image size should be 468 x 60. Flash player must be available on the client's machine in order to display the image.
Text	The text to be displayed at the bottom of the AhsayOBM / AhsayACB client.
Text Animation	Setting to define whether the text should scroll. <ul style="list-style-type: none"> • Scroll Left – text scrolls from right to left. • Scroll Right – text scrolls from left to right. • None – do not scroll text.
Text Alignment	Setting to define the text alignment.

	<ul style="list-style-type: none">• Left – text is aligned left.• Center – text is centered.• Right – text is aligned right.•
URL	The URL of the ad. If the user clicks the ad. in AhsayOBM / AhsayACB, a browser will open and displays this web page.
Enable Tracking	When selected, every time the user clicks the advert in the AhsayOBM / AhsayACB client, a "Hits" counter is incremented.
Seconds	The number of seconds to display the ad.

9 Manage System User (Reseller Panel)

This chapter describes how you can use different function under the [Manage System User] menu to manage the system users within AhsayOBS.

9.1 My Profile / Edit System User

When you click the [Manage System User] - > [My Profile] link available at the top menu, the [My Profile] form will be shown. You can then update system user profile to the system by submitting this form to AhsayOBS. The panel will display differently depending on the role of current login system user.

Admin Role

Admin Role system user has the highest authorization level, all system and backup users can be accessed by Admin role system user at all times. On AhsayOBS only the "system" user possesses the Admin role.

Manage System Manage Log Manage User Manage Group Policy Manag
My Profile Add System User List System User
System User Settings
Login Name : system
Role : Admin
Password : *****
Key :
Login Name Login Name used to logon to web interface.
Role Role of system user
Password Password used to logon to web interface.

Non Admin Role

Non Admin role system user shares the similar accessibility as its creator except with read permission only (Descendant system users and backup users of its creator could be accessed). If Non Admin role system user needs to have the same User Control Policy Settings as its creator, remember to add the Non Admin role system user in the same user group as its creators.

Manage System Manage Log Manage User Manage Group Policy Manage System User	
My Profile Add System User List System User	
System User Settings	
Login Name	: non-admin
Role	: Non Admin
Password	: <input type="password" value="....."/>
<input type="button" value="Update"/> <input type="button" value="Reset"/>	
Key :	
Login Name	Login Name used to logon to web interface.
Role	Role of system user
Password	Password used to logon to web interface.

Sub Admin Role

Sub Admin role system user can access all descendant system users and backup users. When Single Level Access is enabled, system users are restricted to only accessing their own created system users, backup users of system users. Please refer to section 4.5 for more details about Single Level Access Settings.

Manage Log Manage User Manage Group Policy Manage System User		Administ
My Profile Add System User List System User		
System User Settings		
Login Name	: sub-admin	
Role	: Sub Admin	
Password	: <input type="password" value="....."/>	
Name	: <input type="text"/>	
Email	: subadmin@yourcompany.com	
Host Name	: backup.yourcompany.com	
<input checked="" type="checkbox"/> SMTP Settings		
SMTP Server	: Host Name	Login Name Password
	New mail2.yourcompany.com	<input type="text"/> <input type="password"/>
Report Sender	: Name Email Backup Client	
	New Backup Report	@yourcompany.com <input checked="" type="checkbox"/> <input checked="" type="checkbox"/> <input checked="" type="checkbox"/> <input checked="" type="checkbox"/>
<input type="checkbox"/> Customize Interface		
Upload Customization File	: <input type="text"/> <input type="button" value="Browse..."/>	
<input type="button" value="Update"/> <input type="button" value="Reset"/>		

Note:

Backup user accounts created by "sub admin" system users are only supported by AhsayOBM and AhsayACB v6.3.0.0 or above clients.

9.2 SMTP Settings

[SMTP Settings] is available for Sub Admin role system user only. When [SMTP Settings] is enabled, user reports and system reports for current Sub Admin role system user and the associated backup users will be sent through system user defined SMTP server instead of default SMTP server defined at [Manage System] -> [Server Configuration] panel. Report sender contact information can be separated for OBM and ACB backup clients. A maximum of one report sender contact information can be defined for each backup client type.

9.3 Customize Interface

[Customize Interface] is available for Sub Admin role system users only. This option allows Sub Admin role system users to customize their web interface, documentation and company logo in email report at their own preference.

Default customization files are compressed into custom.zip file and can be downloaded from the key section (circled in RED). It consists of three folders for different customization formats, "css" for web style sheets; "pdf" for documentations and "gif" for logos. Customization will be effective once "custom.zip" is uploaded. Language code is enforced on .css and .pdf customization files. Please specify language code and appended it to the end of the file (e.g. jsp_en.css, jsp_da.css, obs-admin-guide_en.pdf, obs-admin-guide_da.pdf), system default settings will be used if language code cannot be found from uploaded files. Previous uploaded customized file can be downloaded again for further modification (circled in BLUE).

Please refer to the section of "Branding AhsayOBS" in this document for the use of customization files.

Manage Log | Manage User | Manage Group Policy | **Manage System User** | Administrator's Guide | Select Language

My Profile | Add System User | List System User | Log Out

SMTP Settings

SMTP Server :

Host Name	<input type="text" value="192.168.101.198"/>	Login Name	<input type="text" value="root"/>	Password	<input type="password" value="..."/>
New	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="password"/>	<input type="password"/>

Report Sender :

Name	<input type="text" value="Report Sender"/>	EEmail	<input type="text" value="jason@bml.168.101"/>	Backup Client	<input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/>
New	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/>	

Customize Interface

[Download Customization File](#)

Upload Customization File :

Key :

Login Name	Login Name used to logon to web interface.
Role	Role of system user
Password	Password used to logon to web interface.
Name	Contact name of system user shown in the system email report
Email	Contact email of system user. Once this setting is set, the system email report will send to this email address.
Host Name	The host name/IP address that backup users will use to contact this server (e.g. backup.company.com) .The backup user login name cannot be duplicated under the same host name.
SMTP Server	List of SMTP servers that will be used to deliver all email reports.
Report Sender	The email address that will be used to deliver backup reports and system reports.
Download Customization File	Previous uploaded customization file is preserved and can be downloaded for further modification.
Upload Customization File	Please download default customization file , modify and upload for interface customization. Customization file "custom.zip" consists of three folders for different customization formats. "css" for web style sheets; "pdf" for documentations and "gif" for logos. Customization will be effective once uploaded. Language code is enforced on "css" and "pdf". Please specify language code and append to end of file (i.e. jsp_en.css and obs-admin-guide_en.pdf), system default setting will be used if language code cannot be found.

A description of all fields above is provided in the following table.

Key	Description
Login Name	Login Name of current system user.
Role	Role of the current system user.
Password	Password of the current system user used to logon to web interface.
Name	Email report contact name of the current system user.
Email	Email address of the current system user.
Host Name	A resolvable hostname of dedicated for the current system user. (e.g. backup.company.com). Although you can supply an IP address here, Login name cannot be duplicated under the same host name.
SMTP Server	The SMTP server that AhsayOBS will use to deliver its email reports to current system user and backup users of current system user.
Report Sender	The name and email address that will be used as a sender for all outgoing mails to backup users of current system

	user. A maximum of two different report senders can be defined for AhsayOBM and AhsayACB users separately.
Upload Customization File	Upload AhsayOBS web customization file 'custom.zip' to the system.

9.4 Add System User

When you click the [Manage System User] -> [Add System User] link available at the top menu, the [Add System User] panel will be shown. This panel allows user to add a Sub Admin or Non Admin role system user to the system. This panel is similar to the [My Profile] page under [Manage User] setting, except that user has the choice to select the [Role] on this page. The SMTP settings will be inherited to its associated users.

9.5 List / Remove System User

When you click the [Manage System User] -> [List System User] link located at the top menu, the [List System User] panel will appear. This panel allows you to list and access all other system users within your authority. You can use the alphabet categories at the top of the user listing to filter the listing to show those users whose login name starting with a certain alphabet. You can also use the [ALL] function to list all system users.

When you click the [Login Name] link available on the system user list, the [System User Settings] panel will appear for system user profile editing. When you click the [Role] link available on the system user list, the system user list will be filtered again by the selected system user. When you click the chain of system user list link under the alphabet categories (circled in RED), the system user list will be filtered again by the selected system user.

No.	Login Name	Role	Name	Email	Host Name	Backup User	
1	Non Admin User2	Non Admin	--	--	--	--	
2	Sub Admin User3	Sub Admin	--	--	192.168.6.129		
3	Sub Admin User4	Sub Admin	--	--	192.168.6.129	--	

Some definitions of the fields related are shown in the following table:

Key	Description
Chain of System User Login Names	It is shown by click on the role column in the [Manage System Users] Page. You can filter a list of accessible system users of the selected system user by clicking on the login name link on the chain.

Login Name	Login Name of the system user. Clicking [Login Name] link to access system user profile.
Role	Role of the system user. Select system user by clicking [Role] link to filter accessible system users of selected system user.
Name	Email report contact name of the system user.
Email	Email address of the system user.
Host Name	Host name/IP address assigned to the system user.
Backup User	Display in AhsayOBM and AhsayACB icons to indicate system user has one or more backup users. Clicking on the icon to view the list of backup users owned by the selected system user.
Owner	The owner of the corresponding system user.
Remove	To remove a system user from the system, just press the  link next to the system user that you would like to remove. The recycling bin appears when the system user has created one or more system users or backup users.

For sub admin accounts the  link will only be visible if there are no existing dependencies for the sub admin accounts, i.e. system and backup users created by this account. If you wish remove a sub admin account, you will need to remove all system and backup users accounts by this particular sub admin account.

10 Managing Backup Users

This chapter describes how you can use all pages under the [Manage User] menu to manage the backup users within AhsayOBS.

10.1 Create Backup User

When you click the [Manage User] -> [Add User] link available at the top menu, the [Add User] form will appear (see below). You can then add a backup user to the system by submitting this form to AhsayOBS.

The screenshot shows the 'Add User' form in the Ahsay Offsite Backup Server interface. The form is divided into several sections:

- User Settings:** Includes fields for Login Name, Password, Alias, Timezone (dropdown), Language (dropdown), Backup Client (dropdown), Assigned Adgroups (radio buttons for 'Do not show any advertisement to this user' and 'Only the following Adgroups:'), Type (dropdown), Email, and Welcome email (checkboxes for 'Send welcome email to new users' and 'Include encrypted password in welcome email').
- Backup Settings:** Includes 'User Home' (text area), 'Backup Quota' (dropdown), and 'Bandwidth' (dropdown).
- Add-on Modules:** A list of modules with checkboxes, including Microsoft Exchange Server, Oracle Database Server, Microsoft SQL Server, Lotus Domino, Lotus Notes, In-File Delta, Volume Shadow Copy, Microsoft Exchange Mailbox, AhsayOBM JVM Royalty, Delta Merge, Continuous Data Protection, ShadowProtect System Backup, and Microsoft Windows System Backup.

Buttons for 'Add' and 'Reset' are located at the bottom right of the form.

A description of all fields above is provided in the following table.

Key	Description
Login Name	Login Name of the new backup user.
Password	Password of the new backup user.
Alias	Another name of the new backup user.
Time zone	Time zone of the new backup user.
Language	Preferred language for all email reports of the new backup user.
Backup Client	Choose AhsayOBM client or AhsayACB client.
Assigned Adgroups	Choose whether advertisements are displayed at the bottom of the backup client.

Type	<p>Either [Trial] or [Paid] type. Trial accounts and paid users differ in the following ways:</p> <ol style="list-style-type: none"> 1. Trial users can only have a maximum backup quota of 500MB within the trial period. 2. Trial users subject to automatic removal as defined by the [Free Trial Registration] setting (though automatic removal can be disabled). <p>Other than the differences listed above, both trial and paid users are the same in all other areas.</p>
Email	Email address of the new backup user.
Welcome email	Define whether a welcome email should be sent to the new user email address.
User Home	<p>The top directory where the software stores backup files and all other information for the new account. If you want this user to be in another partition (or in another drive), please add another user home to AhsayOBS by using the [Manage System] -> [System Configuration] page.</p> <p>If you want to setup your user home directories to a network drive, please do refer to our FAQs section for more information.</p>
Backup Quota	Backup Quota of the new account.
Bandwidth	Bandwidth allowed for the new account.
Add-on Modules	<p>Whether to enable any of the add-on modules to the new backup user.</p> <p>The [Microsoft Exchange Mailbox] text field defines the number of exchange mailboxes that is allowed to be backed up under this user account.</p>

10.2 List / Remove Backup User

When you click the [Manage User] -> [List User] link available at the top menu, the [List User] panel will appear. You can use the alphabet categories at the top of the user listing to limit the listing to show only those users whose login names starting with a certain alphabet. You can also use the [All] function available to list all users within the system.

To remove a user from the system, just press the link next to the user you would like to remove.

The screenshot shows the 'Manage User' section of the Ahsay Offsite Backup Server. It features a navigation menu on the left with options like 'Introduction', 'Getting Started with AhsayOBM', and 'System Management'. The main content area displays a table of users with columns for 'No.', 'User Add-on Modules', 'Login Name (Alias)', 'Registration Date', 'Trial Expiry Date', 'Used / Quota (%)', and 'Owner'. Below the table, there is a section for editing the company logo and software names.

No.	User Add-on Modules	Login Name (Alias)	Registration Date	Trial Expiry Date	Used / Quota (%)	Owner
1		OBM User1 ()	2009-10-02 (Today)	Never Expire	8.38M / 50M (16%)	--
2		OBM User2 ()	2009-10-02 (Today)	Never Expire	0 / 50M (0%)	Sub Admin User2
3		OBM User3 ()	2009-10-02 (Today)	Never Expire	0 / 50M (0%)	Sub Admin User3

Key	Description
Search By	Define whether alphabetically search should be applied to [Login Name] or [Alias].
User Add-on modules	Indicates the add-on modules for this account.
Login Name (Alias)	Login Name of this account. Click the link to see account details. The name in blankets is the alias, and the icon indicates the client type (AhsayOBM or AhsayACB).
Registration Date	Date when this account was created.
Trial Expiry Date	The expiry date of trial users. If it expires, the user account will be suspended. Paid users will show "Never Expire" in this field.
Used/Quota (%)	The used/allocated quota (and the quota usage percentage) of this backup user.
Owner	Owner of this backup user.
Remove	Remove this backup user.
Export Users' Usage Statistics to CSV	Export all users' usage statistics to a .csv file.
Broadcast Message	Use this option if you want to broadcast messages to backup users.

10.3 Broadcast messages to backup users

After you press the [Broadcast Message] link on the top right hand corner of the [Manage User] -> [List User] panel, you will be brought to the [Broadcast Message] page. You can use this page to broadcast messages to different types of backup users.

Key	Description
From	Sender of this message
To	Broadcast message to the following users types: <ul style="list-style-type: none"> All – all backup users Paid – backup users of [Paid] user type Trial – backup users of [Trial] user type AhsayOBM User - backup users of AhsayOBM client type AhsayACB User – backup users of AhsayACB client type Admin – backup administrator, i.e. email address defined on the [Manage System] -> [System Configuration] -> [Administrator Contact] list (useful if you want to test the broadcast feature before sending the message out to all users).
Subject	Subject of this message
Message	Content of this message
Text/HTML	The content type of this message, i.e. whether content should be considered as plain text or HTML.
Attachment	A file to be broadcasted with this message.



--	--

10.4 Managing User Profile

After you press the user name link on the [Manage User] -> [List User] panel, you will be brought to the [User Profile] for this particular user. You can use this panel to update the profile of this user.

This panel is no different to the [User Profile] panel that users will see when they logon to the user areas except that you can now update the [Type], [Quota] and [Add-on Module] (shown in RED) entries on this page.

Click the [File Validation Option] link to rebuild this user's storage information. When a rebuild user jobs is started, AhsayOBS will check if there is an active job running on the backupset before a rebuild is performed on the backupsets. If a backup job is active, the rebuild user storage job will skip rebuilding the active backupset, this will be recorded in the AhsayOBS system log.

2249	09:47:18 PM	test1	--	[info][system][BackupSetBFS.rebuildBFS] Rebuilding User='test1' BSet='1300766064953' Job='2011-03-22-21-00-01'
2250	09:47:18 PM	test1	--	[info][system][BackupSetBFS.rebuildBFS] Rebuilding User='test1' BSet='1300766064953' Job='Current'
2251	09:47:18 PM	test1	--	[info][system][BackupSetBFS.rebuildIndexDir] Rebuilding User='test1' BSet='1300766064953' Job='Current' Directory='/data/user/test1/files/1300766064953/Current/root'
2252	09:47:18 PM	test1	--	[info][system][BackupSetBFS.rebuildBFS] Rebuilding User='test1' BSet='1300785135934' Job='2011-03-22-17-13-28'
2253	09:47:18 PM	test1	--	[info][system][BackupSetBFS.rebuildBFS] Rebuilding User='test1' BSet='1300785135934' Job='2011-03-22-17-13-55'
2254	09:47:18 PM	test1	--	[info][system][BackupSetBFS.rebuildBFS] Rebuilding User='test1' BSet='1300785135934' Job='Current'
2255	09:47:18 PM	test1	--	[info][system][BackupSetBFS.rebuildIndexDir] Rebuilding User='test1' BSet='1300785135934' Job='Current' Directory='/data/user/test1/files/1300785135934/Current/root'
2256	09:47:45 PM	test1	--	[info][system][BfsManager.rebuildUserBFS] The rebuild is skipped on the running backup set ESXi4(1300930261358) of user test1
2257	09:47:45 PM	test1	--	[info][system]Thread-40 [SingleUserRebuild] Finished single user rebuild. User='test1' Owner="" DataSize(compressed)=3.02G DataSize=14.09G DataFileNo=60 RetentionSize(compressed)=3.73M RetentionSize=24.12M RetentionFileNo=65

The information message "[info][system][BfsManager.rebuildUserBFS] The rebuild is skipped on the running backup set ESXi4(1300930261358) of user test1" is recorded when a backupset is skipped.

Note:

- i. **When a rebuild user storage is run on a user account with active backupsets, the calculations for the storages statistics may not reflect the actual storage used as all active backupsets are skipped.**
- ii. **For issues relating to incorrect storage statistics, please make sure the rebuild user storage job is run when no backup jobs are active.**
- iii. **If all backup sets under a user accounts need to be rebuilt, it is recommended that a single rebuild user storage job is started at least 45 minutes after the completion of the last backup job.**

You can reset a user password by entering a new password in [User Profile] -> [Password] -> [New] entry and press the [Update] button. Even though the user password has been updated, both old and new passwords will be temporarily valid, until the user connects to AhsayOBS via AhsayOBM/AhsayACB with the new password. This is because a copy of the user's old password is still saved on the client machine. It's required by AhsayOBM/AhsayACB scheduler service to connect to AhsayOBS in order to run scheduled backups in the interim period.

The [Microsoft Exchange Mailbox] text field defines the number of exchange mailboxes allow to be backed up under this backup account. The [Max] message indicates the maximum number of remaining licenses available.

The [Bandwidth] option allows you to set a maximum network usage for all running backup sets of this particular backup account. All backup sets will

share the same bandwidth defined by this setting. If you have set the bandwidth to be 128kbits/second and there are two backup sets running at the same time, each backup set will share roughly half of the bandwidth assigned, i.e. 64kbits/second.

The [Notes] field allows you to attach some other information, e.g. telephone number or billing address, with this backup account.


Any updates made to the user profile will trigger:

- i.** A "Settings Change Report" will be sent to the user (if the routine job is enabled).
- ii.** A log entry of the change will be recorded in the [Manage System] -> [Manage Log] -> [System Log]
- iii.** A log entry of the change will be recorded in the [Manage System] -> [Manage User] -> [%USERNAME%] -> [User Log]

10.5 Managing Backup Set

After pressing on the link of the selected user on the [Manage User] -> [List User] panel, a [Backup Set] link is now available in the extended user menu. You can review the backup sets setting of this particular user by clicking the [Backup Set] link.

To update the backup set setting of this particular user, just make the required changes on the form below and press the [Update] button.




The screenshot displays the 'Backup Set' configuration interface for 'BackupSet-0'. The interface includes a sidebar with navigation options and a main configuration area. The main area is divided into several sections:

- Name:** BackupSet-0
- Type:** File
- Backup Source:** A list of paths to backup, including 'C:\Documents and Settings\user\My Documents'. There are 'Add' and 'Remove' buttons for each entry.
- Backup Schedule:** No schedules defined.
- Backup Set - Options:**
 - Enable In-File Delta:** A checkbox that is currently checked.
 - Block Size:** Set to 'Auto' (Bytes).
 - Minimum Size:** Set to '25' (Mbytes).
 - Enable delta merge:** An unchecked checkbox.
 - Default In-file Delta Type:** Set to 'Differential' (Advanced).
 - Upload Full File when Maximum No. of Delta greater than:** Set to '100' (-1 = Unlimited).
 - Upload Full File when Delta Ratio greater than:** Set to '50' (Delta Size / File Size (%)).
- Temporary Directory:** C:\Documents and Settings\user\temp. There is a checkbox for 'Enable Delete Temp. File' which is checked.
- Retention Customization Policy:** Set to '7' (Days). There is a 'Customize' option.

Setting Online Restore IP Restriction

At the bottom of the [Backup Set] panel, you should be able to find the [Online Restore IP Restriction] section. If you would like to restrict online file restore of this backup set to only a subset of trusted IP addresses, you just need to enter the trusted IP addresses here. Once you have entered some IP addresses into the IP restriction list, online file restore request originating from IP addresses into the IP restriction list, online file restore request originating from IP addresses not listed on this list will no longer be able to restore any files from this backup set. (You can use the IP range of 127.0.0.1 – 127.0.0.1 to disable online restore completely).



Global Backup Set Values

The following values are only valid for Group Policy enforcement and default backupsets only, do not use these values in normal backupsets.

Value :	Description
<code>\${lotus.notesini}</code>	Notes INI path
<code>\${mac.desktop}</code>	Desktop directory in Mac OS
<code>\${mac.documents}</code>	Documents directory in Mac OS
<code>\${mac.movies}</code>	Movies directory in Mac OS
<code>\${mac.music}</code>	Music directory in Mac OS
<code>\${mac.pictures}</code>	Pictures directory in Mac OS
<code>\${mysql.mysqlbackup}</code>	MySQL backup path
<code>\${sys.KEY}</code>	KEY is the name of the System Property e.g. <code>\${sys.user.home}</code> is the home directory of the user
<code>\${win.desktop}</code>	Desktop directory in Windows
<code>\${win.favorites}</code>	Favorites directory in Windows
<code>\${win.mail}</code>	User data of Outlook Express or Windows Mail (Windows Vista / Windows 7 / Windows Server 2008 / Windows Server 2008 R2) in Windows
<code>\${win.mydocuments}</code>	My Documents directory in Windows
<code>\${win.outlook}</code>	User data of Outlook in Windows
<code>\${winenv.KEY}</code>	KEY is the name of the Windows Environment Variable e.g. <code>\${winenv.SYSTEMDRIVE}</code> is the drive containing the Windows root directory (C: by default)
<code>\${winreg.KEY}</code>	KEY is the name of the Windows Registry Key e.g. <code>\${winreg.HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\ShadowProtectSvc\ImagePath}</code> is the value of ShadowProtect installation path

10.6 Initiating Backup from AhsayOBS

While end users can initiate backup jobs from their computers by using manual or scheduled backup jobs from AhsayOBM or AhsayACB. The AhsayOBS server administrator can initiate a backup job from AhsayOBS web console. In order to initiate a backup job go to the [Manage User] -> [Run Backup], and you will have something similar in the following screenshot:

The screenshot shows the Ahsay Offsite Backup Server web console. The top navigation bar includes 'Manage System', 'Manage Log', 'Manage User', 'Manage Group Policy', and 'Manage System User'. The current page is 'Run Backup' for the user 'Sub Admin User2'. A search bar is present with options for 'Login Name' and 'Alias'. Below the search bar is a table listing backup sets for the user.

No.	Login Name (Alias) ->	Backup Set	Backup is pending	Backup Type	Used / Quota (%)	Last Backup	Owner
1	ACB User2				0 / 50M (0%)		Sub_Admin User2
	<input type="checkbox"/>	Default	No			No backup has been run	
2	OBM User2				0 / 50M (0%)		Sub_Admin User2

Below the table are two buttons: 'Run Backup' and 'Cancel Backup'. On the left side of the console, there is a sidebar with navigation links: 'Switch to Ahsay™ Replication Server', 'Introduction', 'Understanding Ahsay Online Backup Suite', 'Getting Started with AhsayOBM', 'Getting Started with AhsayACB', 'Key Features', 'Documentations', 'System Management', and 'Contact us'. At the bottom of the console, there is a text box with instructions: 'Edit [INSTALL_FOLDER] \webapps \ROOT \lib \common.js to customize your company logo and the names of softwares. After that, you can delete the content of "RenameProcedure" to remove this line.' Below this text box are two placeholder boxes for 'Your Company Logo'.

Some definitions of the fields related are shown in the following table:

Key	Description
No.	Number count of user.
Login Name (Alias) -> Backup Set	The login name of the user with the alias bracketed behind. If there is any backup set, the name of the backup set will be shown under the user login name.
Backup is pending	"Yes" if the backup job is pending after pressing [Run Backup]; Otherwise "No".
Backup Type	Type of backup. For files only backup, the backup type will be empty.
Used / Quota (%)	The used data size of the user on the server and the total quota of data size that the user can use. The percentage of used size over quota is bracketed behind.
Owner	Owner of this backup user.
Last Backup	The creation time of the latest backup.

In order to use this feature:

- The AhsayOBM/AhsayACB scheduler service must be running on the client machine and can connect to the AhsayOBS server.
- The "Run scheduled backup on computers named" field on the backupset must be filled in with the correct computer name of the client machine.

To initiate a backup job from AhsayOBS, check the box next to each of the required backupsets. Then press the [Run Backup] button at the bottom of the page. The status of [Backup is pending] of the chosen backup sets will be changed to "Yes", and after a short time AhsayOBM/ AhsayACB will start backing up the data sources from the specific machine.

When the backup is finished, the status of [Backup is pending] will become "No", and the [Last backup] will be update with date and time of the last backup job.

10.7 Browsing User Backup File

You can click the [File Explorer] link available at the extended [Manage User] menu to invoke the [File Explorer] panel. You can use this panel to browse and restore user's backup files. This panel is the same [File Explorer] panel that users would see when they click the [File Explorer] link after they have logged on to the system. Please refer to the User's Guide for information on how to restore users' backup files.



The screenshot shows the Ahsay Offsite Backup Server File Explorer interface. The top navigation bar includes links for 'Manage System', 'Manage Log', 'Manage User', 'Manage Group Policy', 'Manage System User', and 'user'. Below this, there are links for 'Add User', 'List User', 'Run Backup', 'User Profile', 'Backup Set', 'File Explorer', 'Report', 'Statistics', and 'User Log'. The main content area is divided into two sections. The left section contains a navigation menu with items like 'Switch to Ahsay™ Replication Server', 'Introduction', 'Understanding Ahsay Online Backup Suite', 'Getting Started with AhsayOBM', 'Getting Started with AhsayACB', 'Key Features', 'Documentations', 'System Management', and 'Contact us'. The right section displays a table of backup sets. The table has columns for 'Backup Set', 'Size', 'Last Modified', and 'Zipped (Ratio)'. A single backup set, 'Backup Set-0', is listed with 'Restore' and 'Delete' buttons. Below the table, a 'Note' section provides instructions: 1. This shows all backup sets available within this backup account. 2. To restore backup files, please click the [Restore] button shown above. 3. To delete a backup set, please click the [Delete] button shown above. At the bottom of the page, there are two yellow boxes labeled 'Your Company Logo'.

10.8 Reviewing User Backup Report

You can click the [Report] link available at the extended [Manage User] menu to invoke the [Report] panel. You can use this panel to review users' backup activities. This panel is the same [Report] panel that users would see when they click [Report] link after they have logged on to the system. Please refer to the User's Guide for information on how to review users' backup activities.

The screenshot shows the Ahsay Offsite Backup Server interface. The top navigation bar includes links for Manage System, Manage Log, Manage User, Manage Group Policy, Manage System User, and a dropdown for user selection. The main content area displays a report for a backup job completed successfully on 2009-10-02 at 15:27. The job status is 'Backup finished successfully' and the backup time is '2009/10/02 15:27 - 2009/10/02 15:28 (HKT)'. Two tables provide statistics for the backup job and the user account.

Backup Job Statistics		User Account Statistics	
New Files*	59 [8.11M bytes]	Data Area**	8.11M bytes / 36.74M bytes
Updated Files*	0 [0 bytes]	Retention Area**	0 bytes / 0 bytes
Updated Access Permissions*	0 [0 bytes]	Total Upload	8.11M bytes
Deleted Files*	0 [0 bytes]	Backup Quota	50M bytes
Moved Files*	0 [0 bytes]	Remaining Quota	41.89M bytes

* Unit = Number of files [Total file size]
** Unit = Compressed Size / Uncompressed Size

To review CDP backup reports instead of selecting the backup time, select "(CDP)", as CDP backup jobs are constantly active the job status prior to the daily cut off at 12:00 AM is "Backup not yet finished"

The screenshot shows the Ahsay Offsite Backup Server interface with the backup set changed to 'File with CDP' and the backup job selected as '(CDP)' for 2011-01-20. The job status is 'Backup not yet finished' and the backup time is '2011/01/20 12:17 - 2011/01/20 12:17 (HKT)'. Two tables provide statistics for the backup job and the user account.

Backup Job Statistics		User Account Statistics	
New Files*	0 [0 bytes]	Data Area	36k bytes
Updated Files*	0 [0 bytes]	Retention Area	0 bytes
Updated Access Permissions*	0 [0 bytes]	Total Upload	44k bytes
Deleted Files*	0 [0 bytes]	Backup Quota	50G bytes
Moved Files*	0 [0 bytes]	Remaining Quota	50G bytes

* Unit = Number of files [Total file size]

10.9 Reviewing User Storage Statistics

You can click the [Statistics] link available at the extended [Manage User] menu to invoke the [Statistics] panel. You can use this panel to review users' storage statistics. This panel is the same as the [Statistics] panel that users would see when they click the [Statistics] link after they have logged on to the system. Please refer to the User's Guide for information on how to review user' storage statistics.

Storage Usage Summary Month (YYYY-MM): 2009-09

Date	Data Area*	Retention Area*	Uploaded Size*	Total Storage*
2009-09-11	178k [7]	0 [0]	178k [7]	178k [7]
2009-09-12	178k [7]	0 [0]	0 [0]	178k [7]
2009-09-13	178k [6]	0 [0]	0 [0]	178k [6]
2009-09-14	178k [6]	0 [0]	0 [0]	178k [6]
2009-09-15	178k [6]	0 [0]	0 [0]	178k [6]
2009-09-16	178k [6]	0 [0]	0 [0]	178k [6]
2009-09-17	7.91M [55]	0 [0]	7.73M [49]	7.91M [55]
2009-09-18	452k [21]	41k [1]	1.38M [62]	493k [22]
2009-09-22	4.26M [107]	111k [9]	7.01M [190]	4.37M [116]
2009-09-23	4.26M [107]	111k [9]	0 [0]	4.37M [116]
2009-09-24	4.26M [107]	111k [9]	0 [0]	4.37M [116]
2009-09-25	4.26M [107]	111k [9]	0 [0]	4.37M [116]
Average	2.2M [45]	40k [3]	1.36M [25]	2.24M [48]

* Unit : Compressed Size [Total No. of Files]

Key:

- Data Area** Total backup data stored in the data area
- Retention Area** Total backup data stored in the retention area. Old copies of updated or deleted backup files are retained here for the number of days specified by the retention policy of the backup set before they are removed from the system.
- Uploaded Size** Total data uploaded on a particular date
- Total Storage** Data Area + Retention Area

```

Edit [INSTALL_FOLDER] \webapps \ROOT \lib \
common.js to customize your company logo and the
names of softwares. After that, you can delete the
content of "RenameProcedure" to remove this line.
    
```

Your Company Logo

User statistics are calculated on a daily basis by the "Usage Report" system job. If the "Usage Report" is disabled or if your AhsayOBS service is offline when the "Usage Report" system job is due to run, no user statistics will be calculated for those days. AhsayOBS cannot calculate user statistics for past days which have been missed.

10.10 User Log

You can click the [Statistics] link available at the extended [Manage User] menu to invoke the [User Log] panel. You can use this panel to review the user specific activities on the AhsayOBS server.

Manage System | Manage Log | **Manage User** | Manage Group Policy | Manage System User **[ACBUser_B1_1]** Select Language

Add User | List User | Run Backup | User Profile | Backup Set | File Explorer | Report | Statistics | **User Log** Logout

Date (YYYY-MM-DD) : 2010-09-29 Rows/Page: 50

No.	Timestamp	Message
1	10:18:25 AM	[info][user][UpdateUserProfile] IP="127.0.0.1", [USER (Before) RESET_PWD="****" -> (After) RESET_PWD="****"].
2	10:42:49 AM	[info][user][UpdateUserProfile] IP="127.0.0.1", [USER (Before) RESET_PWD="****" QUOTA="53687091200" -> (After) RESET_PWD="****" QUOTA="10737418240"].

A copy of user related activities can also be seen in the AhsayOBS system log, under [Manage System] -> [Manage Log] -> [System Log].

11 Group Policy Management

This chapter describes how you can use the [Manager Group Policy] menu to manage your user groups on AhsayOBS.

Term	Descriptions
Policy Control	Areas that are affected by group policy
Policy Group	A group of preset policy control objects
User Group	A group of users.

11.1 About Group Policy

The Group Policy feature is designed to simplify administration and to reduce the effort required for managing backup users, e.g. security settings and backup set settings. It allows backup server administrator a greater degree of flexibility in tailoring features and services to target specific customer segments.

User Groups

When Group Policy is implemented on AhsayOBS, the backup user accounts will be consolidated into common user groups. Each user group will have its own set of policy groups which govern behaviour of the backup clients. The types of features that can be configured from a policy group are restricting or hiding certain functions or features on AhsayOBM/AhsayACB user interface or the AhsayOBS web console.

For example, a backup service provider wishes to offer customers a cut rate service plan, i.e. "OBM Basic Plan", which consists of fixed quota limit and where customer cannot change backupset settings. The service provider will create a user group on AhsayOBS called "OBM Basic Plan". To customize the features for each group, a policy group will need to be created called "OBM Basic Plan Policy", which will contain a group share quota setting and a Policy Control Setting for AhsayOBM to disable access to some AhsayOBM controls.

[OBM Basic Plan Policy] → [OBM Basic Plan]

Once the policy group "OBM Basic Plan Policy" is assigned to user group "OBM Basic Plan", it will be effective immediately. Any AhsayOBM users that are assigned to the "OBM Basic Plan" group will be governed by the "OBM Basic Plan Policy" settings.

Policy Controls

The policy controls which can be customized for each user group are:

1. Shared Quota Settings

A maximum quota or "Shared Size" can be specified for each user group via a policy group setting, each backup user assigned to the user group will automatically be allocated a portion of this quota, according to the "Maximum percentage of shared size for each user" value.

2. Backupset Configuration

- Define a default backupset for AhsayOBM/AhsayACB users who belong to the group.
- Define an enforcement backupset for AhsayOBM/AhsayACB users who belong to the group. When an Enforcement backupset is configured for a backupset type, it will overwrite all settings on any pre-existing backupset types.

3. Policy Control Setting

The Policy Control Setting allows the backup server administrator to customize the user interface for AhsayOBM/AhsayACB and AhsayOBS user web console interface according to each user group.

4. Global Filter Setting

This setting defines a global file filter for AhsayOBM and AhsayACB backupsets which belong to the user group. The backupsets which can be configured with global filtering on AhsayOBM are restricted to File, CDP, Lotus Domino, and Lotus Notes backupsets. When a global filter is applied to a user group, any the pre-existing backupset filters will be overwritten by the global filter.

11.2 Best Practices for using Group Policy

In order to avoid any confusion and for better AhsayOBS server administration, it is recommended to keep the group policy design as simple as possible:

1. One-to-One relationship between policy and user group. Each policy group should only be applied to one user group.
2. One-to-One relationship between user account and user group. Each user should only belong to one user group.
3. Active user accounts should not be transferred between user groups.
4. New user groups and policies should be thoroughly tested before they are implemented on a production server.
5. A separate policy should be created for each type of policy type.

E.g. A policy name "AhsayOBS – Read-only Main Menu" for policies that restrict the users to have Read-Only access on main menu.

E.g. a user group named "AhsayOBS – System User Read-Only Main Menu" for a user group with "AhsayOBS – Read-only Main Menu" policy assigned.

6. The naming conventions for user groups and policies should be meaningful and easily distinguishable. Example: For a new user group called "ACB Premium" group which has some restrictions to the AhsayACB UI interface control and features. The associated policy group would be called "ACB_Premium_UI".
7. Once a user group is operational, i.e. user accounts have been assigned and backups are running according to the policy settings, there should be no further policy changes.
8. For user groups defined with shared quota policy, please make sure the sum of the individual user backup quota does not exceed the shared size. For example, a group with a shared quota policy defined as, shared size of 500GB and maximum percentage of shared size for each user of 25% (125GB). Should only have a maximum of four backup users assigned to it (125GB x 4 users = 500GB).
9. Extreme caution must be exercised when assigning policies to user groups. As a policy will be effective and enforced as soon as it is assigned to a group, any errors in policy assignments could result in unforeseen problems for all members of the affected user group.
10. Any backup user accounts which are using v5.5 AhsayOBM/AhsayACB clients on AhsayOBS v6 should not belong to any user groups. As they are not compatible with group policy features.

11.3 Group Policy Limitations and Restrictions

1. Each user group is restricted to only one shared quota policy.
2. Each user group is restricted to only one set of Default and Enforcement backupsets for each backupset type.
3. Each backup user account is permitted to have one Default Backup Set and one Enforcement Backup Set for each available Backup Set Type.
4. Only one Global Filter is allowed for each backupset type.
5. A backup user cannot be a member of more than one user group with shared quota policy enabled.

11.3.1 List Policy Control

There are three main categories for policy control objects AhsayOBS, AhsayOBM, and AhsayACB. Each control object allows the backup server administrator to configure the controls or features which can be accessible or visible to the end user.

All policy control objects can be found in the [Manage Group Policy] -> [Policy Control] Page.



No.	Policy Control	Permissions
1	Manage System Menu	R
2	Manage Log Menu	R
3	Manage User Menu	R
4	Manage Group Policy Menu	R
5	Manage System User Menu	R


AhsayOBS

A group of policy control objects used to control the behaviour of AhsayOBS. The control area defined on AhsayOBS policy control group is in the format of:

[Menu Name] – [Page Name] – [Section Name] – [Section Detail] (if any)

E.g. The name of the policy to control the System Settings section on Server Configuration page under the [Manage System] menu is:

“Manage System – Server Configuration – System Settings”



System Settings

Login Name : system
 Password :
 Host Name : localhost
 System Home : C:\ProjectAhsay\obs\rcbase\system
 Policy Home : C:\ProjectAhsay\obs\rcbase\system\policy
 User Homes : 1. C:\ProjectAhsay\obs\rcbase\user
 New :
 Single Level Access : Limited system users and backup users access on current level and one below

Email System Settings

SMTP Server	Host Name	Login Name	Password
1.	smtp.your-company.com		
New			


AhsayOBM

A group of policy control objects used to control the behaviour of AhsayOBM. The control area defined on AhsayOBM policy control group is in the format of:

[Section Name] – [Section Details] (if any)

E.g. To restrict access to the Recycle Bin under Quota Usage section on the Main Frame, you should edit the settings in this policy:

“Quota Usage – Recycle Bin”



AhsayACB

A group of policy control objects used to control the behaviour of AhsayACB. The control area defined on AhsayACB policy control group is in the format of:

[Section Name] – [Section Details] (if any)

E.g. To restrict access to the Recycle Bin under Quota Usage section on the Main Frame, you should edit the settings in this policy:

“Quota Usage – Recycle Bin”

11.4 User Group

11.4.1 List User

When you click the [Manage Group Policy] -> [List User] Link available at the top menu, the [List User] panel will appear. An overview of user groups and owner on backup can be listed by default backup users are only shown.

Manage System | Manage Log | Manage User | **Manage Group Policy** | Manage System User | Administrator's Guide | Select Language

Policy Control | **List User** | User Group | Policy Group | Policy Assignment | [Logout](#)

Type : Backup user System user

Search by : Login Name Alias

[[A-B](#) | [C-D](#) | [E-F](#) | [G-H](#) | [I-J](#) | [K-L](#) | [M-N](#) | [O-P](#) | [Q-R](#) | [S-T](#) | [U-V](#) | [W-X](#) | [Y-Z](#) | [Others](#) | [Trial](#) | [Paid](#) | [Suspended](#) | [All](#)]

system			
No.	Login Name (Alias)	Owner	User Group
1	a (a)	--	--
2	A1 Backup User (A1 Backup User)	A1	--
3	acb.user.duplicate ()	Duplicate.02	--
4	acb.user.duplicate ()	Duplicate.01	--
5	acb_tester1 (acb_tester1)	--	--
6	acb_tester2 (acb_tester2)	--	--
7	acbee ()	--	--
8	AdgroupTest ()	--	--
9	admin ab.obm.user.01 (admin ab.obm.user.01)	--	--
10	admin abcd.obm.user.01 (admin abcd.obm.user.01)	--	--
11	admin abcd.obm.user.02 (admin abcd.obm.user.02)	--	--
12	Assigned Adgroups ()	--	--
13	Assigned Adgroups ACB ()	--	--
14	b ()	--	--
15	B1 Backup User (B1 Backup User)	B1	--
16	BackupUser01@SA0 ()	SA0	--
17	BackupUser01@SA1 ()	SA1	--
18	BackupUser01@SA2 ()	SA2	--
19	BackupUser01@SA3 ()	SA3	--
20	BackupUser01@SA5 ()	SA5	--
21	BackupUser01@SA6 ()	SA6	--


The system user list can also be listed by selecting the "System user" radio button near the top menu.

Press the [Login Name] link to show the details of policy groups, user groups and owner on selected backup user. The system user detail can also be viewed by similar way.

11.4.2 Manage User Group

[User Group] panel is used to manage the user group's for both backup users and system users. Please click the [Manage Group Policy] -> [User Group] link to enter the [User Group] panel.

The default view shows the available user groups for "backup user". The user group list for "system user" can also be listed by selecting the "System user" radio button near the top menu.



Owner : --

Type : Backup user System user

User Group : User Group - Read Only - Backup User Add Remove

Name: User Group - Read Only - Backup User

Users

No user has been assigned to this user group yet.

[Assign users](#)

Update Reset

Key :
Users Assign system user or backup user to this user group

The user group feature can be used obtain information on how many users accounts have been assign to a user group.



Owner : --

Type : Backup user System user

User Group : LimitQuota Add Remove

Name: LimitQ

Users

Users assign

No.	LimitQuota	Owner
1	quota (abc123)	--

Update Reset

Key :
Users assigned to this user group Shows backup users assigned to this user group.

You can use the combo box to list the number of existing user groups defined. After selecting the desired user group all user accounts assigned to this group will be displayed.

[Manage System](#) | [Manage Log](#) | [Manage User](#) | **[Manage Group Policy](#)** | [Manage System User](#)
[Administrator's Guide](#) | [Select Language](#)

[Policy Control](#) | [List User](#) | **[User Group](#)** | [Policy Group](#) | [Policy Assignment](#)
[Logout](#)

Owner : --

Type : Backup user System user

User Group :

Name:

Users

Users assigned to this user group [[Edit](#)]

No.	Login Name (Alias)	Owner	
1	 quota (abc123)	--	
2	 test1 ()	--	
3	 test2 ()	--	
4	 test3 ()	--	

Key :
Users assigned to this user group Shows backup users assigned to this user group.

Create user group

[Manage System](#) | [Manage Log](#) | [Manage User](#) | **Manage Group Policy** | [Manage System User](#)
[Policy Control](#) | [List User](#) | **User Group** | [Policy Group](#) | [Policy Assignment](#)

Owner : --

Type : Backup user System user

User Group : User Group - Read Only - Backup User

Name:

Users
 No user has been assigned to this user group yet.
[Assign users](#)

Key :
Users Assign system user or backup user to this user group

Please follow the instructions below to create a user group:

1. Go to the [User Group] panel.
2. Select the user group type, i.e. Backup user or System user.
3. Press the [Add] button.
4. Change the default name to a more descriptive user group name.
5. Press the [Updated] button to complete the process.

Remove an existing user group

[Manage System](#) | [Manage Log](#) | [Manage User](#) | **Manage Group Policy** | [Manage System User](#)
[Administrator's Guide](#) | [Select Language](#)

[Policy Control](#) | [List User](#) | **User Group** | [Policy Group](#) | [Policy Assignment](#)
[Logout](#)

Owner : --

Type : Backup user System user

User Group :

Name:

Users

Users assigned to this user group [[Edit](#)]

No.	Login Name (Alias)	Owner	
1	BackupUser01@SA1 ()	SA1	

Key :
Users assigned to this user group Shows backup users assigned to this user group.

To remove a user group, please do the followings:

1. Go to the [User Group] panel.
2. Select the user group from the drop down list.
3. Press the [Remove] button to remove the user group.

WARNING:

The remove user group feature will remove the selected user group from AhsayOBS even if:

- i. **There are active user accounts assigned to the group**
- ii. **There are active policies assigned to the group**

All member user accounts upon removal of the user group will be automatically unassigned. Once unassigned, the user accounts will retain the policy restrictions of the removed user group.

It is strongly recommended prior to removing a user group, to ensure that all member user accounts are re-assigned first.

Assign Users to a user group

Manage System | Manage Log | Manage User | **Manage Group Policy** | Manage System User Administrator's Guide | Select Language

Policy Control | List User | **User Group** | Policy Group | Policy Assignment Logout

User Group : User Group - Read Only - Backup User
 Owner : --
 Type : Backup user

Search by : Login Name Alias

[**A-B** | C-D | E-F | G-H | I-J | K-L | M-N | O-P | Q-R | S-T | U-V | W-X | Y-Z | Others | Trial | Paid | Suspended | All]

system			Owner
No.	<input type="checkbox"/>	Login Name (Alias)	
1	<input type="checkbox"/>	a (a)	--
2	<input type="checkbox"/>	A1 Backup User (A1 Backup User)	A1
3	<input type="checkbox"/>	acb.user.duplicate ()	Duplicate.02
4	<input type="checkbox"/>	acb.user.duplicate ()	Duplicate.01
5	<input type="checkbox"/>	acb_tester1 (acb_tester1)	--
6	<input type="checkbox"/>	acb_tester2 (acb_tester2)	--
7	<input type="checkbox"/>	acbee ()	--
8	<input type="checkbox"/>	AdgroupTest ()	--
9	<input type="checkbox"/>	admin ab.obm.user.01 (admin ab.obm.user.01)	--
10	<input type="checkbox"/>	admin abcd.obm.user.01 (admin abcd.obm.user.01)	--
11	<input type="checkbox"/>	admin abcd.obm.user.02 (admin abcd.obm.user.02)	--
12	<input type="checkbox"/>	Assigned Adgroups ()	--
13	<input type="checkbox"/>	Assigned Adgroups ACB ()	--
14	<input type="checkbox"/>	b ()	--
15	<input type="checkbox"/>	B1 Backup User (B1 Backup User)	B1
16	<input type="checkbox"/>	[Suspended] BackupUser01@SA0 ()	SA0
17	<input type="checkbox"/>	BackupUser01@SA1 ()	SA1
18	<input type="checkbox"/>	BackupUser01@SA2 ()	SA2
19	<input type="checkbox"/>	BackupUser01@SA3 ()	SA3
20	<input type="checkbox"/>	BackupUser01@SA5 ()	SA5
21	<input type="checkbox"/>	BackupUser01@SA6 ()	SA6

Please follow the instructions below to assign users to a specific user group:

1. Go to the [User Group] panel.
2. Select a user group from the dropdown box.
3. Click the [Assign users] link located in the [Users] section to go to the user list. This option is only shown when the list is empty.
4. If the list is not empty, please click on the [Edit] link in the [User] section.
5. Select users from the user list by checking the checkboxes and vice versa.
6. Press the [Update] button to add selected backup users to backup user group.

Remove Users from a user group

To remove users from a user group, please do the followings:

1. Go to the [User Group] panel.
2. Select a user group from the dropdown box.
3. Press the  link next to the backup user you would like to remove or press the [Edit] link located in the [Users] section to enter the user list section.

Note:

You can use the alphabet categories at the top of the backup user list to limit the list to show only those backup users whose login name starting with a certain alphabet. You can also user the [Owner] link to limit the listing to show backup users belong to the selected owner.

11.5 Policy Group

11.5.1 Manage Policy Group

When you click the [Manage Group Policy] -> [Policy Group] link available at the top menu, the [Policy Group] form will appear. This is used to define policies for backup users or system users.

The default view shows the available Policy Groups for "backup user". The Policy Groups list for "system user" can also be listed by selecting the "System user" radio button near the top menu.

[Manage System](#) | [Manage Log](#) | [Manage User](#) | **[Manage Group Policy](#)** | [Manage System User](#)
[Administrator's Guide](#) | [Select Language](#)

[Policy Control](#) | [List User](#) | [User Group](#) | **[Policy Group](#)** | [Policy Assignment](#)
[Logout](#)

Owner : --

Type : Backup user System user

Policy Group : Policy Group - Backup User Policy

Name :

Shared Quota Setting [Show Options](#) ▾

Backup Set Setting [Show Options](#) ▾

Policy Control Setting [Show Options](#) ▾

Global Filter Setting [Show Options](#) ▾

Key :

Shared Quota Setting	The disk quota shared by all users. If it is enabled, backup is stopped if the total disk usage of users in this group exceeds the specified quota or the total disk space of this user group. A user can only be assigned to one group with this feature enabled.
Backup Set Setting	Each user group can have one backup set type and one operations system of default backupset for AhsayOBM and AhsayACB users. Each user group can have one backup set type of enforcement backupset for AhsayOBM and AhsayACB users. When enforcement backup set is used, the existing backup set of AhsayACB user will be overwritten by the enforcement backup set.
Policy Control Setting	the policy control assigned to users
Global Filter Setting	Each user group can have one backup set type and one operations system of global filter for AhsayOBM and AhsayACB users. When global filter is used, the existing filters in the backup sets will be overwritten by the global filter.

Create a policy group

To create a new policy group, please do the followings:

1. Go to the [Policy Group] form.
2. Select the backup user type, i.e. Backup user or system user
3. Change the name to a more descriptive policy group name.
4. Press the [Update] button to save the changes.

Remove an existing policy group

Please do the followings to remove a policy group:

1. Go to the [Policy Group] form.
2. Select the policy group from the drop down list.
3. Press the [Remove] button to remove the policy.

Below is a table showing the available policy types that can be assigned to a policy group.

Policy Group Type	Available Policy Types
Backup User	- Shared Quota Policy Control - Backup Set Setting Policy Control - Backup User Policy Control - Global Filter Policy Control
System User	- Share Backup Users Policy Control - System User Policy Control

11.5.2 Shared Quota Policy

Shared Quota Policy is available for Backup User Policy Group only. It is used to define a maximum storage limit for a particular group, which is evenly allocated to each individual backup user within the group. Each backup user is allocated a fixed percentage of the total storage limit.

The advantage of using a share quota policy is it will simplify user home storage management. For example, if users for a group where assigned an individual user home drive, this setting will ensure the backup users cannot user more disk space than is physically available on the drive.



Assign Shared Quota Policy to a policy group

1. Go to the [Policy Group] form.
2. Select a Backup User Policy Group from the drop down list.
3. Click the [Show Options] link at the right side of the [Shared Quota Setting] section. The information of shared quota policy will be shown.
4. Check the checkbox next to the [Disk quota share].
5. Fill in the [Shared Size] and [Maximum percentage of shared size for each user] field.
6. Press [Update] button to save the changes.

Reset Disk quota share

1. Go to the [Policy Group] form.
2. Select a Backup User Policy Group from the drop down list.
3. Click the [Show Options] link at the right side of the [Shared Quota Setting] section. The information of shared quota policy will be shown.
4. Uncheck the checkbox next to the [Disk quota share] to reset it to default.
5. Press [Update] button to update the changes.

When implementing a shared quota policy, you need to take into account any additional users assigned to the group will result in the reduction of backup quota for existing users and therefore impact on the backups operation of these users. So the "shared size" will have to be adjusted in order to ensure sufficient space for the additional users.

For example, if "Group VIP" was assigned a shared size of 100GB, with a maximum percentage of 20% for each user in the group. Initially 5 AhsayOBM users are assigned to Group VIP, the backup quota for each individual user will be 20GB. For this setup each user can fully utilize their individual backup quotas without affecting others in the group.

But if another 5 users were assigned to Group VIP, they too will be allocated 20GB each of backup quota. This will mean if all users fully utilize their backup quota's (10 users X 20GB = 200GB), it will exceed the shared size of 100GB. In this scenario, the first 5 backup users to who fully utilize their backup quotas, will cause the other 5 users backup jobs to fail with a "*Group Quota Exceeded. Please contact us to increase your quota.*" error.

11.5.3 Backup Set Setting Policy

Backup Set Setting Policy is available for Backup User Policy Group only. It is used to pre-define the backup settings for backup users. This helps to pre-fill backup settings when backup users creates a new backup set (called "Default Backup Set") whereas other helps to enforce backup setting to backup users. This is known as an "Enforcement Backup Set".

Default Backup Set




The screenshot shows the 'Backup Set Setting' interface. At the top, there is a header bar with 'Backup Set Setting' on the left and 'Show Options ^' on the right. Below the header, there is a sub-header '[Help] Default Backup Set'. The main content area is divided into two columns for 'AhsayOBM Users [Edit]' and 'AhsayACB Users [Edit]'. Under the 'AhsayOBM Users' column, there is a 'Backup Set Type' section with a tree view containing 'File', 'Windows', 'Mac OS X', 'Linux', 'Microsoft SQL Server', and 'Microsoft Exchange Server'. Each item in the tree has a corresponding dropdown menu in the 'AhsayOBM Users' column. The 'AhsayACB Users' column has empty dropdown menus for each of these categories.

Note:

User cannot assign a higher level default backup set to a lower level policy group, i.e. If a user (User1) is created by a sub-admin role system user, and there is a default backup set policy (Policy 1) created by a admin role system user. "Policy 1" cannot be assigned to User1.

Enforcement Backup Set



Create a Pre-defined Backup Setting Policy

1. Go to the [Policy Group] form.
2. Select a Backup User Policy Group from the drop down list.
3. Click the [Show Options] link at the right side of [Backup Set Setting] section to show the information of [Default Backup Set] and [Enforcement Backup Set] sub-sections.
4. If you are going to create a "Default Backup Set", click the [Edit] link next to [AhsayOBM Users] or [AhsayACB Users] in the [Default Backup Set] sub-section to show the default backup set form. Otherwise, click the [Edit] link next to the [AhsayOBM Users] or [AhsayACB Users] in the [Enforcement Backup Set] sub-section to show the enforcement backup set form.
5. Click the [Add] button to create a new backup set.
6. Fill in the necessary field(s) in the backup set form and click the [Update] button to save the changes.

[Manage System](#) | [Manage Log](#) | [Manage User](#) | [Manage Group Policy](#) | [Manage System User](#) | [Administrator's Guide](#) | [Select Language](#)
[Policy Control](#) | [List User](#) | [User Group](#) | **Policy Group** | [Policy Assignment](#) | [Logout](#)

Backup Set:

[\[Help\]](#) **Name**

[\[Help\]](#) **Type**
 File Microsoft SQL Server Microsoft Exchange Server
 Oracle Database Server MySQL Database Server
 Lotus Domino Lotus Notes System State
 Microsoft Exchange Mail Level Backup ShadowProtect System Backup
 Microsoft Windows System Backup

[\[Help\]](#) **Backup Source**
 Backup the following files/directories :
 1.
 Exclude the following files/directories :
 1.

[\[Help\]](#) **Backup Schedule**
 No schedules defined

Backup Set - Options

[\[Help\]](#) **Enable In-File Delta**
 Block Size : Bytes
 Minimum Size : Mbytes
 Enable delta merge
 Default In-file Delta Type :
 Upload Full File when Maximum No. of Delta greater than : (-1 = Unlimited)
 OR
 Upload Full File when Delta Ratio greater than : Delta Size / File Size (%)

[\[Help\]](#) **Temporary Directory**
 Temporary directory for storing backup files :
 Enable Delete Temp. File

Remove a Pre-defined Backup Setting Policy

1. Go to the [Policy Group] form.
2. Click the [Show Options] link at the right side of [Backup Set Setting] section to show the information of [Default Backup Set] and [Enforcement Backup Set] sub-sections.
3. To delete a "Default Backup Set" setting, click the [Edit] link next to [AhsayOBM Users] or [AhsayACB Users] in the [Default Backup Set] sub-section. Otherwise, click the [Edit] link next to [AhsayOBM Users] or [AhsayACB Users] in the [Enforcement Backup Set] sub-section.
4. Select the backup set from the drop down list.
5. Click the [Remove] button to remove it from the system.

Assign a Pre-defined Backup Set to a Default Backup Setting policy

6. Go to the [Policy Group] form.
7. Click the [Show Options] link at the right side of [Backup Set Setting] section to show the information of [Default Backup Set] and [Enforcement Backup Set] sub-sections.
8. Select the pre-defined backup set from drop down.
9. Click the [Update] button to save the changes.

11.5.4 Backup User Policy Control

Backup User Policy Control is available to Backup User Policy Group only. It is used to restrict the backup users' access privileges on AhsayOBS, AhsayOBM and AhsayACB. By default, full access privilege is granted. A summary of access permission is listed below:



Permission	Meanings
R	Read
W	Write
E	Execute
D	Delete

Edit Policy Control

1. Go to the [Policy Control] form.
2. Click the [Show Options] link at the right side of [Policy Control Setting] section to show the permission information on [AhsayOBS], [AhsayOBM] and [AhsayACB] sub-sections.
3. Click the [Edit] link next to the [Group] drop down list to go to the policy control selection.
4. Select the Policy Control that you would like to edit by checking the checkbox on the left side of the Policy Control ID, and the corresponding RWXD checkboxes will be enabled.
5. To assign access permission to a Policy Control, select/de-select the checkbox under the RWXD section.

Policy Type	Permission
Read-only	R
Editable	RW
Editable and Executable	RWE
Modifiable	RWD
Full	RWED
Hidden	All checkboxes are unchecked

6. Click the [Update] button to save the changes.

Remove Policy Control

[Manage System](#) | [Manage Log](#) | [Manage User](#) | **[Manage Group Policy](#)** | [Manage System User](#)
[Administrator's Guide](#) | [Select Language](#)

[Policy Control](#) | [List User](#) | [User Group](#) | **Policy Group** | [Policy Assignment](#)
[Logout](#)

Policy Group: Policy Group - Backup User Policy

Owner : --

Type : Backup user

Product :  AhsayOBS


Group : User-User Profile

	No.	Policy Control	R	W	X	D
<input type="checkbox"/>	1	Manage User-User-User Profile Menu				
<input type="checkbox"/>	2	Manage User-User-User Profile-User Summary				
<input type="checkbox"/>	3	Manage User-User-User Profile-Alias				
<input type="checkbox"/>	4	Manage User-User-User Profile-Language				
<input type="checkbox"/>	5	Manage User-User-User Profile-Timezone				
<input type="checkbox"/>	6	Manage User-User-User Profile-Contact				
<input type="checkbox"/>	7	Manage User-User-User Profile-Add-on Modules				
<input type="checkbox"/>	8	Manage User-User-User Profile-Quota				
<input type="checkbox"/>	9	Manage User-User-User Profile-Update Reset Button				

1. Go to the [Policy Control] form.
2. Click the [Show Options] link at the right side of [Policy Control Setting] section to show the permission information on [AhsayOBS], [AhsayOBM] and [AhsayACB] sub-sections.
3. Press the  link next to the policy control that you would like to remove.
4. The Policy Control is now removed from the system.

11.5.5 Global Filter Policy

Global Filter Policy is applied to system users only. It is used to set pre-defined backup filter to backup users.



Manage System | Manage Log | Manage User | **Manage Group Policy** | Manage System User | Administrator's Guide | Select Language

Policy Control | List User | User Group | **Policy Group** | Policy Assignment | Logout

Filter : Filter-File-Windows-OBM Normal [Add] [Remove]

Name
Filter-File-Windows-OBM Normal

Operating System
Windows

Backup Set Type
File

Type
 Include Exclude

Apply to
 File Directory

Top Directory
C:\

Matching Criteria
File/Directory name with the following patterns:
 Start with End with Contain Unix-style Regular Expression
Existing Pattern 1: .doc
Add New Pattern: []

For example:
Choose "End with" along with ".doc" as pattern to match all Microsoft Word documents.

Option
For those unmatched files/directories under top directory above:
 do nothing
 exclude them if "Include" type, include them if "Exclude" type

[Update] [Reset] [Back to Group Policy]

Create global filter policy


1. Go to the [Policy Control] form.
2. Click on the [Show Options] link in the [Global Filter] section.
3. Click the [Edit] link next to [AhsayOBM Users], [CDP Filter for OBM Users] or [AhsayACB Users].
4. Click the [Add] button to create a new policy.
5. Select the [Operating System] and [Type], then press the [Update] button.
6. Fill in the required information shown in the page.
7. Press the [Update] button to save the changes.

Delete global filter policy

1. Go to the [Policy Group] panel.
2. Click the [Edit] link next to [AhsayOBM Users], [CDP Filter for OBM Users] or [AhsayACB Users].
3. Select the policy from the drop down box.
4. Press [Remove] button to remove it from the system.

11.5.6 Shared Backup User Policy

Shared Backup User Policy is only available to System Users Policy Group. It helps Sub Admin role system users to share their backup users provided they are under the same creator.



The screenshot shows the configuration page for a policy group. At the top, there are navigation links: Manage System, Manage Log, Manage User, Manage Group Policy (highlighted), Manage System User, Administrator's Guide, and Select Language. Below these are breadcrumb links: Policy Control, List User, User Group, Policy Group (highlighted), and Policy Assignment, along with a Logout link.

The main configuration area includes:

- Owner: --
- Type: Backup user System user
- Policy Group: Policy Group - System User Policy (dropdown menu) with Add and Remove buttons.
- Name: Policy Group - System User Policy (text input field)
- Shared Backup Users Setting section with a Show Options link and a checked Backup Users Share checkbox.
- Policy Control Setting section with a Show Options link.
- Update and Reset buttons.
- Key section:

Backup Users Share	Backup users will be shared and maintain by group of system users
Policy Control Setting	the policy control assigned to users

Edit Shared Backup User Policy

1. Go to the [Policy Group] panel.
2. Select the system user radio button for the user type.
3. Click the [Show Options] link in the [Shared Backup Users Setting] section to show the information of shared backup user policy.
4. Check the [Backup User Share] checkbox to share the backup users, uncheck it to reset to default.
5. Press the [Update] button to update the change.

11.5.7 System Users Policy Control

The System User Policy Control is available to System User Policy Group only. It is used to restrict the system users' access privileges on AhsayOBS. By default, full access privilege is granted. A summary of access permission is listed below:

Permission	Meanings
R	Read
W	Write
E	Execute
D	Delete

Edit Policy Control

1. Go to the [Policy Control] form.
2. Select [System User] radio button.
3. Click the [Show Options] link at the right side of [Policy Control Setting] section to show the permission information on [AhsayOBS] sub-sections.
4. Click the [Edit] link next to the [Group] drop down list to go to the policy control selection.
5. Select the Policy Control that you would like to edit by checking the checkbox on the left side of the Policy Control ID, and the corresponding RWXD checkboxes will be enabled.
6. To assign access permission to a Policy Control, select/de-select the checkbox under the RWXD section.

Policy Type	Permission
Read-only	R
Editable	RW
Editable and Executable	RWE
Modifiable	RWD
Full	RWED
Hidden	All checkboxes are unchecked

7. Click the [Update] button to save the changes.

Remove Policy Control

1. Go to the [Policy Control] form.
2. Select the [System User] radio button.
3. Click the [Show Options] link at the right side of [Policy Control Setting] section to show the permission information on [AhsayOBS] sub-sections.
4. Press the  link next to the policy control that you would like to remove.
5. The Policy Control is now removed from the system.

12 Delta Merge Technology

12.1 Introduction

The delta merge feature combines the full and incremental delta files on AhsayOBS into a single full file. The advantage of using delta merge is it will speed up the restore of files. As a single (merged) file full can be restored faster than a file consisting of full plus related incremental files, which will require a lengthy merging process after restoring to a client machine.

Delta merge only applies to full and **incremental delta files** which reside in the **data area only**. The criteria for file merging is governed by the retention policy setting for the backupset, delta merge will not work if there is more than one encryption key in use for a backupset. It is supported by AhsayOBM/AhsayACB v6.3 or above clients, there is no delta merging feature for Local Copy backups.

12.2 Delta Merge Policy

The delta merge process relies on the retention policy setting to decide when to merge incremental delta files with the full file. But delta merge does not apply to files in the retention area. Any reference to retention policy in the context of delta merge implies delta merge policy. As backupsets enabled with delta merge share a single setting, any changes in retention policy will impact on the availability of snapshots that can be restored from both data and retention area. Before enabling the delta merge feature please review your data restore requirements carefully.

Once a backupset is delta merge enabled, other in-file delta related settings such as "Upload Full File when Maximum No. of Delta greater than: xx", "Upload Full File when Delta Ratio greater than: xx%", and advanced in-file delta will no longer apply.

12.3 Delta Merge Process

A delta merge will take place after a backup job is completed, AhsayOBM/AhsayACB will only initiate a delta merge request at the end of a backup job, if there has been an incremental delta upload. As part of the request, AhsayOBM/AhsayACB will upload a copy of the backupset encryption key to AhsayOBS which is hashed for security purposes. Once a merge request is received by AhsayOBS it will be placed in the "delta merge queue".

A background job is used on AhsayOBS to identify any incremental delta files that are out of retention period and merge them with the full file, this process handles one merge operation at a time. When AhsayOBS processes a file merge request, it first checks if a delta merge has been performed on a backupset within the last 24 hours. If this condition is true the delta merge

request will be skipped, otherwise the merge process will be carried according to the retention policy.

The 24 hour period is calculated from the start time of the previous delta merge and the start time of the current merge.

Each delta merge operation is recorded in the AhsayOBS system logs. The following is an example of delta merge activity which is recorded under [Manage System] -> [Manage Log] -> [System Log].

1138	01:55:00 PM	m1	--	[info][system][Thread][Job][MergeDelta] Start merging delta files in backup set 'b1' of user 'm1'.
1139	01:55:00 PM	m1	--	[info][system][Debug:DeltaMerge] user = m1, backup set id = 1300288285909, size of jobs = 2, < retention period 2
1140	01:55:00 PM	m1	--	[info][system][Thread][Job][MergeDelta] Finished merging delta files in backup set 'b1' of user 'm1'.

The following is an example of a system log entries when a delta merge has taken place within the last 24 hours.

1211	02:37:00 PM	m1	--	[info][system][Thread][Job][MergeDelta] Skip merging delta files of user 'm1', backup set 'b1' because that backup set has run delta merge in last 24 hours.
1212	02:37:00 PM	m1	--	[info][system][Thread][Job][MergeDelta] Finished merging delta files in backup set 'b1' of user 'm1'.

Although, delta merge requests are submitted to AhsayOBS immediately after the completion of a backup job. In some situations it could take a few days before a merge request is finally processed. The actual execution of the merge requests is dependent factors such as:

- i. The number of backupsets with delta merge enabled.
- ii. The number of requests pending in the merge queue.
- iii. The type and size of full and delta files which are pending to be merged, i.e. ESXi, Hyper-V, Shadow Protect backupsets which may take longer to merge.
- iv. Performance of your AhsayOBS server

12.4 Delta Merge Queue

The delta merge queue details are saved in the following file %OBS_HOME%\conf\mergeQueue.xml. Once a job in the merge queue has been completed, the request will be immediately removed from the merge queue. AhsayOBS will then process the next request in the queue.

The following is an example of a delta merge queue record:

```
<queue><Merge Name="m1" ID="1300288285909" Key="y8nPnJyc"
Owner=""/></queue>
<queue><Merge Name="test1" ID="1200256285881" Key="cjLONXyt"
Owner=""/></queue>
```

Field	Description
Name	Backup user account
ID	BackupSet ID
Key	Hashed encryption key used for the delta merge
Owner	The sub admin account which created the backup user (if applicable)

WARNING: Do not edit the contents of this file

12.5 Limitations

Delta merging only applies to incremental deltas backupsets with differential delta settings cannot use this feature. For backupsets which were created under AhsayOBM/AhsayACB v5.5, which may contain differential delta's. Delta merging will not be applied to these backupsets.

For example, a file backupset on AhsayOBS v5.5.8.0 consists of one full, one differential, and two incremental delta files in the data area.

5.5.8.0	6.3.0.0
F + D + I ₁ + I ₂	I ₃ + I ₄ + I ₅ + I ₆

If both AhsayOBS and the AhsayOBM client are upgraded to v6.3 and delta merging is enabled. Subsequent backup jobs where incremental delta files are uploaded (I₃ + I₄ + I₅ + I₆) will not result in any delta merge, regardless of the delta merge policy. In order for delta merge to apply, the differential delta file must be removed from the delta chain. This will be done when the next full file upload to AhsayOBS is performed, which will result in the previous full file and delta chain moving to retention area. Alternatively, you can create a new backupset instead so delta merge can be used almost immediately.

For AhsayACB user accounts the in-file delta and delta merge features are still dependent on AhsayOBS global settings, under [Manage System] -> [Other Options] -> [In-file delta settings for all AhsayACB users]. Therefore,

all AhsayACB users are limited to either using delta merge or traditional incremental/differential delta model.

Even though the delta merge job processes one backupset at a time. For delta merge enabled backupsets which contain very large files, i.e. Exchange, MS SQL, Domino, Oracle , MS System backup, Windows 2008 SystemState, ShadowProtect, ESXi, and Hyper-V. **It is strongly recommended user home drives containing these backupsets should maintain at least 30% to 40% free disk space. As the delta merge process generates temporary copies of both the full and incremental file on the user home drive. If the user home runs out of disk space, it could result in corruption of both the full and incremental file, in the worse case the data of any other active backupsets could also be compromised.**

12.6 Delta Merge Examples

The following is some simple examples to demonstrate the functionality of the delta merge feature:

Example 1:

The example below shows how delta files are merged into full file using a retention policy (delta merge policy) setting defined as 4 jobs for this backup set.

A full backup file is stored into data area (F) uploaded by Job 1, followed by incremental delta files I_1 , I_2 , I_3 , and I_4 . On the completion Job 5 (I_4), AhsayOBM/AhsayACB will trigger a delta merge background job to execute the file merging. When the AhsayOBS delta merge job runs $F + I_1$ will be merged to become a "merged" full file. The data area now contains 4 snapshots including merged full file after file merging.

Retention Policy = 4 Jobs (Delta Merge Policy)

Job 1 = F
Job 2 = I_1
Job 3 = I_2
Job 4 = I_3
Job 5 = I_4 (delta merge initiated)

After job 5 AhsayOBM/AhsayACB will initiate a delta merge for Job 1 & Job 2 files.

F ($F + I_1$) merged full file
 I_2
 I_3
 I_4

Example 2:

The example below shows how delta files are merged into full file using a retention policy (delta merge policy) setting defined as 7 days for this backup set.

A full backup file is stored into data area (F) uploaded on Day 1, followed by incremental delta files I₁, I₂, I₃, I₄, I₅, I₆, I₇, and I₈. On the completion of the backup job on Day 9 (I₈), AhsayOBM/AhsayACB will trigger a delta merge background job to execute the file merging. When the AhsayOBS delta merge job runs F + I₁ will be merged to become a "merged" full file. The data area now contains 8 snapshots including merged full file after file merging.

Retention Policy = 7 Days (Delta Merge Policy):

Day 1 = F
Day 2 = I₁
Day 3 = I₂
Day 4 = I₃
Day 5 = I₄
Day 6 = I₅
Day 7 = I₆
Day 8 = I₇
Day 9 = I₈ (delta merge initiated)

After job on day 9 AhsayOBM/AhsayACB will initiate a delta merge for Day 1 & Day 2 files. As the incremental file I₁ has exceeded the 7 day retention policy setting.

F (F + I₁) merged full file
I₂
I₃
I₄
I₅
I₆
I₇
I₈

Example 3:

This example below shows what happens when there are multiple backup jobs occurring which generates incremental delta files within a 24 hour period.

A full backup file is stored into data area (F) uploaded by Job 1, followed by incremental delta files I_1 , I_2 , I_3 , and I_4 . On the completion Job 5 (I_4), AhsayOBM/AhsayACB will trigger a delta merge background job to execute the file merging. When the AhsayOBS delta merge job runs $F + I_1$ will be merged to become a "merged" full file.

Retention Policy = 4 Jobs (Delta Merge Policy)

Job 1 = F
Job 2 = I_1
Job 3 = I_2
Job 4 = I_3
Job 5 = I_4 (delta merge initiated)
Job 6 = I_5
Job 7 = I_6

After job 5 AhsayOBM/AhsayACB will initiate a delta merge for Job 1 & Job 2 files. If after the delta merge there are further incremental uploads, i.e. Job 6 and Job 7. These increment files will not be merged by AhsayOBS as a delta merge jobs has already taken place within the last 24 hours. The data area now contains 6 jobs, which exceeds the delta merge policy of 4 jobs

F ($F + I_1$) merged full file
 I_2
 I_3
 I_4
 I_5
 I_6


AhsayOBS will merge the extra incremental files, when the next backup job completes 24 hours after the last delta merge. AhsayOBS will merge all the delta files which have exceeded the backupset delta merge policy.

13 Account Lockout

When the account lockout feature is enabled, a backup user account will be locked after three consecutive failed login attempts. The account lockout restriction applies unsuccessful logins via AhsayOBS web console, AhsayOBM, AhsayACB, and AhsayRDR web console. The account lockout restrictions do not apply to "system", "sub admin", and "non admin" account types. **To enhance security on AhsayOBS, the account lockout feature is enabled by default.**

13.1 Configuration


The status of the account lockout feature is shown in the AhsayOBS web console under the [Manage System] -> [Server Configuration] -> [Auto Lock User].



The screenshot shows the 'System Settings' page in the AhsayOBS web console. The 'Auto Lock User' setting is checked, indicating that the account lockout feature is enabled. The settings are as follows:

Login Name	: system
Password	: [REDACTED]
Host Name	: localhost
System Home	: E:\AhsayOBS and AhsayRPS\system
Policy Home	: E:\AhsayOBS and AhsayRPS\system\policy
User Homes	: 1. E:\AhsayOBS and AhsayRPS\user New [REDACTED]
Single Level Access	: <input type="checkbox"/> Limited system users and backup users access on current level and one below
Auto Lock User	: <input checked="" type="checkbox"/> Lock backup user automatically after 3 invalid login attempts

To disable the AhsayOBS account lockout feature, simply uncheck the "Auto Lock User" setting and press the [Update] button. This setting will be effective immediately.



The screenshot shows the 'System Settings' page in the AhsayOBS web console. The 'Auto Lock User' setting is unchecked, indicating that the account lockout feature is disabled. The settings are as follows:

Login Name	: system
Password	: [REDACTED]
Host Name	: localhost
System Home	: E:\AhsayOBS and AhsayRPS\system
Policy Home	: E:\AhsayOBS and AhsayRPS\system\policy
User Homes	: 1. E:\AhsayOBS and AhsayRPS\user New [REDACTED]
Single Level Access	: <input type="checkbox"/> Limited system users and backup users access on current level and one below
Auto Lock User	: <input type="checkbox"/> Lock backup user automatically after 3 invalid login attempts

Even though the account lockout feature is disabled, any backup user accounts which were locked prior to the disabling of this feature will still remain locked. These backup user accounts will have to be enabled by either a "system" or "sub admin" user.

Note:

For AhsayRDR implementations, the account lockout configuration must be aligned on all member AhsayOBS servers.

13.2 Account Lockout Rules

For each unsuccessful login attempt via AhsayOBS web console, AhsayRDR web console, AhsayOBM, or AhsayACB. The account lockout counter will increase by 1. After three consecutive unsuccessful login attempts the backup user account will be locked.

The account lockout counter will reset to zero if one of the following conditions are met:

- User logs on successfully via AhsayOBS web console, AhsayOBM/AhsayACB or AhsayRDR web console.
- Change the user [Status] from "Locked" to "Enabled" or "Suspended" in [Manage User] -> [User Profile] page.

The "system" or "sub admin" users cannot manually lock a backup user account. An account lockout can only be triggered by consecutive failed login attempts.

Once an account is locked, all AhsayOBM/AhsayACB client scheduler(s) and CDP service(s) connecting to AhsayOBS using the locked account will automatically be stopped, they will not re-connect to AhsayOBS again until after another six hours, even if the affected account is enabled immediately.

If a scheduled or manual backup job has started prior to the account "locked" status, these backup jobs will continue as normal until completion. This behavior will also apply to restore, seed load, and decrypt operations.

WARNING:

If there are any backup jobs which are scheduled to start within this six hour period they will not be run, these jobs will be classified as a missed backups.


If you wish to minimize the problem of missed backups, you can consider restarting the AhsayOBM/AhsayACB scheduler and CDP services on all affected client machines after affected user account is unlocked.

13.3 Unlocking Accounts

Once a backup user account is locked it can only be enabled by either a "system" or "sub admin" user.

To reset the status of a "Locked" backup user, please do the following:

1. Login to AhsayOBS Web Administration Console using a "system" or "sub admin" user account.
2. Go to [Manage Users] -> [List User] page.
3. Find the backup user from the user list and click on the username to view [User Profile].
4. Change the [Status] by checking the [Enable] radio button.
5. Click [Update] to apply the change.




The screenshot shows the user profile configuration page for 'abc123'. The 'Status' section is highlighted with a red circle, showing three radio buttons: 'Enable' (selected), 'Suspended', and 'Locked'. Other visible fields include:

- Alias:** abc123
- Password:** [Hashed] (New: [Clear Text])
- Quota:** 50.0 (kbytes, Mbytes, Gbytes)
- Bandwidth:** Unlimited (Bits/Second)
- Backup Client:** AhsayOBM User
- Assigned Adgroups:** Do not show any advertisement to this user; Only the following Adgroups: Default Adgroup
- Type:** Paid User (Suspend paid user at 2011-12-11)
- Add-on Modules:** Microsoft Exchange Server, Oracle Database Server, Lotus Domino, In-File Delta, Volume Shadow Copy, Microsoft Exchange Mailbox (10), AhsayOBM JVM Royalty, Delta Merge, Continuous Data Protection, ShadowProtect System Backup, Microsoft Windows System Backup, Microsoft Windows Virtualization (10), VMware VM Backup (10)
- Language:** English
- Timezone:** GMT+08:00 (HKT)
- Contact:** 1. Name: abc123 (Remove); Email: support@qa.ahsay.com.local; 2. Name: (Add)

13.4 Account Lockout on AhsayOBS/AhsayRDR

The following is an example of what is displayed when there is an incorrect user login attempt via AhsayOBS web console.



After three consecutive incorrect login attempts the user account will be automatically locked.



13.5 Account Lockout on AhsayOBM/AhsayACB

The following is an example of what is displayed when there is an incorrect user login attempt via AhsayOBM or AhsayACB client.



After three consecutive incorrect login attempts the user account will be automatically locked. The following dialog box will be displayed on the client machine.



AhsayOBM/AhsayACB scheduler logs (debug.log) will show the following error "**[error] Account locked. Please contact your backup service provider. Retry in 6 hours ...**"

debug.log

```
[2011/01/28 20:04:32][info] Loading configuration file ...
[2011/01/28 20:04:32][info] Loading configuration file ... Completed
[2011/01/28 20:04:32][info] Loading profile from server ...
[2011/01/28 20:04:33][error] Account locked. Please contact your backup
service provider. Retry in 6 hours ...
```

13.6 Account Lockout Auditing

Information relating to incorrect logins attempts will be recorded in the AhsayOBS system log, as well as the AhsayOBS logs located in %OBS_HOME%\logs.

The following is an example of what is recorded in the system log, when there is an incorrect user login attempt via the AhsayOBS web console

Login attempts via AhsayOBS web console are identified as "[www][Logon] '%user_account%'"

948	11:00:00 AM	t1	--	[info][www][Logon] 't1' logon failed. IP='10.10.0.1', Login Failure Count=1 , Reason=[UserCacheManager.PasswordIncorrectExpt] Incorrect password for user 't1'.
949	11:00:02 AM	t1	--	[info][www][Logon] 't1' logon failed. IP='10.10.0.1', Login Failure Count=2 , Reason=[UserCacheManager.PasswordIncorrectExpt] Incorrect password for user 't1'.
950	11:00:05 AM	t1	--	[info][www][Logon] 't1' logon failed. IP='10.10.0.1', Login Failure Count=3 , Reason=[UserCacheManager.PasswordIncorrectExpt] Incorrect password for user 't1'.
951	11:00:07 AM	t1	--	[info][www][Logon] 't1' logon failed. IP='10.10.0.1', Reason=[UserCacheManager.UserLockedExpt] User 't1' is locked.

The following is an example of what is recorded in the system log, when there is an incorrect user login attempts from an AhsayOBM/AhsayACB client.

Login attempts via AhsayOBM/AhsayACB are identified as "[system][getProfileRqt] '%user_account%'"

149	04:55:30 AM	t1	--	[info][system][GetUserProfileRqt][UserCacheManager.PasswordIncorrectExpt] Incorrect password for user 't1', IP = '10.10.0.1', Login Failure Count = 1
150	04:55:32 AM	t1	--	[info][system][GetUserProfileRqt][UserCacheManager.PasswordIncorrectExpt] Incorrect password for user 't1', IP = '10.10.0.1', Login Failure Count = 2
151	04:55:34 AM	t1	--	[info][system][GetUserProfileRqt][UserCacheManager.PasswordIncorrectExpt] Incorrect password for user 't1', IP = '10.10.0.1', Login Failure Count = 3
152	04:55:36 AM	t1	--	[info][system][GetUserProfileRqt][UserCacheManager.UserLockedExpt] User 't1' is locked.

14 Multiple Thread Support

Multiple thread support is available for the following AhsayOBM/AhsayACB functions; backup, restore, local copy, seed load, and file decrypt for all backup sets. In order to utilize this feature AhsayOBM and AhsayACB need to be on version v6.3.0.0 or above. In addition, the web restore applet also supports multiple thread file restores for AhsayOBS v6.3.0.0 or above.

Multiple thread support is enabled by default and cannot be disabled. The maximum number of threads supported is automatically determined by the number of logical CPU's on a client machine:

Maximum number of threads = Number of Logical CPU x 2 (up to a maximum of 8 threads)

Multiple threading will result in increased memory and CPU usage on the AhsayOBM/AhsayACB client machine, the level of resource usage will be proportion to the number of active threads. In order to fully leverage this feature, it is recommended a client machine should be installed with multiple core processors and sufficient free memory.

WARNING:

Multiple thread backup and restore operations can result in increase loading on your AhsayOBS server and could lead to AhsayOBS performance problems. It is strongly recommended a review of AhsayOBS hardware and configuration requirements is undertaken, to determine server suitability before mass deployment of v6 clients.

15 Create a “Read Only” or Non Admin System User

To create a read only admin user or non admin user account, go to the [Manage System] -> [Manage System User] page and click on “Add System User” link.

Manage System | Manage Log | Manage User | Manage Group Policy | **Manage System User** Administrator's Guide | Select Language

My Profile | **Add System User** | List System User Logout

System User Settings

Login Name :

Role : Non Admin

Password :

Key :

Login Name Login Name used to logon to web interface.

Role Role of system user

Password Password used to logon to web interface.

Enter the login name for the new system user account, the password must be at least six characters long, and the role must be “Non Admin”.

Manage System | Manage Log | Manage User | Manage Group Policy | **Manage System User** Administrator's Guide | Select Language

My Profile | **Add System User** | List System User Logout

System User Settings

Login Name :

Role : Non Admin

Password :

Key :

Login Name Login Name used to logon to web interface.

Role Role of system user

Password Password used to logon to web interface.

To confirm the creation of the new user press the “Add” button. The account will be created and AhsayOBS will list the new and existing non admin accounts.

Manage System | Manage Log | Manage User | Manage Group Policy | **Manage System User** Administrator's Guide | Select Language

My Profile | **Add System User** | List System User Logout

[[A-B](#) | [C-D](#) | [E-F](#) | [G-H](#) | [I-J](#) | [K-L](#) | [M-N](#) | [O-P](#) | [Q-R](#) | [S-T](#) | [U-V](#) | [W-X](#) | [Y-Z](#) | [Others](#) | [All](#)]

Administrator										
No.	Login Name	Role	Name	Email	Host Name	Backup User	User Group	Policy Group	Owner	
1	readonly	Non Admin	--	--	--	--	--	--	--	
2	readonly1	Non Admin	--	--	--	--	--	--	--	
3	readonly2	Non Admin	--	--	--	--	--	--	--	
4	readonly3	Non Admin	--	--	--	--	--	--	--	
5	readonly4	Non Admin	--	--	--	--	--	--	--	

16 AutoUpdate

This chapter describes how you can use the AutoUpdate feature to automatically update AhsayOBM and AhsayACB to all running instances:

16.1 How it works

The AutoUpdate operation relies on backup scheduler to function properly. No new updates will be delivered to a machine running AhsayOBM or AhsayACB if the backup scheduler is not enabled or no scheduled backup jobs have been run.

AutoUpdate works in the following sequences:

1. The backup scheduler running on the client machine will download the `index.xml` file (`%OBSR_HOME%\webapps\obs\liveUpdate\index.xml`) which contains the information of the latest client software available from AhsayOBS.
2. If the backup scheduler finds that AhsayOBS contains a patch for AhsayOBM or AhsayACB which is newer than the current version, it will download and install the patch from AhsayOBS automatically (`%OBSR_HOME%\webapps\obs\liveUpdate\obm?????.zip`).
3. After the AhsayOBM or AhsayACB client is updated. The scheduled backup job will run using latest version of AhsayOBM.

Note:

In order for AutoUpdate to work the `index.xml` file must be renamed from `index.xml` to `index.xml.disable`

16.2 Using AutoUpdate

When you install an updated version of AhsayOBS on your backup server, a new version of the AutoUpdate module for AhsayOBM is already bundled with the updated version of AhsayOBS. This means that a new version of AhsayOBM or AhsayACB will be delivered to all your client machines through AutoUpdate when you install an updated version of AhsayOBS on your server.

16.3 Customizing AutoUpdate

If you want to customize the AutoUpdate patch file that will be delivered to your existing client installations (i.e. sending your own patch file to your client), please refer to the [Ahsay Customization Portal User Guide](#) from the [Ahsay Customization Portal](#) for more information.

16.4 Forcing an extra AutoUpdate

If you want to customize the AutoUpdate patch file that will be delivered to your existing client installations (i.e. sending your own patch file to your client), please refer to the Ahsay Backup Software Upgrade Guide

16.5 AutoUpdate Limitations

AutoUpdate is officially supported for AhsayOBM & AhsayACB v5.2.8.0 or above to v6.

AutoUpdate of AhsayOBM & AhsayACB to v6 is officially supported for O/S platforms specified in [AhsayPedia Article #2165](#)

AhsayAUA v2 does not support AhsayOBM/AhsayACB upgrade from v5 to v6 on the following O/S platforms:

- i. FreeBSD
- ii. Solaris
- iii. Mac OSX

AhsayAUA may update details on bundled Java that is packaged with AhsayOBM installation. Due to this reason, AhsayAUA will not support upgrades on these platforms as propriety Java are in use.

17 Backup / Restore files using off-line media

Backing up large amount of files (e.g. 300GB) online through the Internet is a very lengthy task. It is sometimes necessary to ship the first full backup through off-line media (e.g. removable USB hard disk) to the backup server. Once the first full backup is loaded onto the backup server through off-line media, all subsequent backups will be able to run and complete successfully in a timely manner because it is only necessary to upload new/updated files to the backup server.

Restoring large amount of files (e.g. 300GB) online through the Internet is also a very lengthy process. It is also important to be able to allow users to restore their backup file through offline media to reduce the time required to restore large amount of files.

This chapter describes the steps required to import/export backup files to/from AhsayOBS.

17.1 Seed loading backup files (Import)

A backup user can use the [Seed Load Utility] to transport its first full backup to an offsite backup server without having to upload a large volume of data through the Internet (Please refer to the [AhsayOBM User's Guide](#) for more information). When the seed load files are transported to the backup server (e.g. using removable hard disk), please follow the instructions below to install them into the required user account:

1. Locate the home directory of the backup user.

A backup user's home directory is a directory named the login name of the backup user under one of the AhsayOBS's [User Homes] directories. [User Homes] is a system-wide setting which can be accessed under the [Manage System] menu after logging onto the web system management console.

For example:

The default [Users Homes] directory is "C:\Program Files\AhsayOBS and AhsayRPS\user". If the login name of the backup account is "john", the home directory of user "john" should be "C:\Program Files\AhsayOBS and AhsayRPS\user\john".

2. Copy all seed load files to the home directory.

Find the "files" directory from the seed load files, and copy the "files" directory to the backup user's home directory.

In this example, you should copy the "files" directory to "C:\Program Files\AhsayOBS and AhsayRPS\user\john"

If you are running AhsayOBS on Linux under a non-root user (e.g. obs), please make sure that the "files" directory and all its contents are owned and writable by the user running AhsayOBS (e.g. obs).

3. Check if all files are installed correctly.

Logon to the web interface of AhsayOBS with the backup user account ("john" in this example) and click the [File Explorer] link available at the top of the menu. Check if you can see all seed load files correctly installed.

4. Total number of files and total file size imported into the data area through seed loading is not visible in the profile of this backup user (i.e. The [User Profile] page still reports no files in the data area). Administrator should run the "File Validation Option" ([AhsayOBS web admin console] -> [Manage User] -> [User Profile] -> [File Validation Option]) for the corresponding user with the option "Verify Checksum" enabled to ensure that all backup files are seed loaded to AhsayOBS correctly.

If you need to perform another import (seed loading) when there are backup files on the backup server already, please remove all existing backup files from the backup server by removing the backup set ID directory (i.e. a numerically named directory under the "files" directory under a user directory) before copying all new seed loading files into the system. If you have more than one backup set ID directory under the "files" directory, please take a look at [User Home Directory]\db\Profile.xml to find out the correct Backup Set ID for the required backup set.

17.2 Saving backup files to off-line media (Export)

If you want to save a copy of all backup files under a backup user account to an offline media, please do the following:

1. Locate the home directory of the backup user.
2. Copy the complete home directory of this backup user to an offline media.
3. Once the offline media is shipped to the user, the user can then use the [Decrypt File Wizard] available in AhsayOBM to decrypt and restore the backup files available in the offline backup back to its original format.

18 High Availability & Load-Balancing Configuration

For further information, please refer to the AhsayOBS High Availability Option Setup Guide and Ahsay Redirector Setup Guide available in our [document section](#).

19 Secure Socket Layer (SSL) Configuration

This chapter describes how you can use the Management Console to configure various settings of AhsayOBS.

19.1 Installing a trusted SSL certificate

Default installation of AhsayOBS enables SSL (Secure Socket Layer) support using a dummy certificate. For your own security, you are advised to replace the pre-installed dummy SSL certificate with a secure SSL certificate from a trusted CS (Certificate Authority). To replace the non-secure dummy SSL certificate with a secure SSK certificate, please do the following:

1. Identify the location of the keystore file.

You need to store your SSL certificate in a keystore file. The default location of the keystore file is %OBSR_HOME%\conf\keystore.

2. Delete dummy certificate from keystore.

You can delete the dummy SSL certificate from the keystore by running:

```
%OBSR_HOME%\java\bin\keytool -delete -alias tomcat -keystore
%OBSR_HOME%\conf\keystore.
```

You will be prompted for the keystore password. The default password is "changeit".

Platform	Example
Windows	<i>C:\Program Files\AhsayOBS and AhsayRPS\conf> "C:\Program Files\AhsayOBS and AhsayRPS\java\bin\"keytool -delete alias tomcat - keystore keystore</i>
Linux	<i>[root]# keytool -delete -alias tomcat -keystore /Applications/AhsayOBS/conf/keystore</i>

3. Generate RSA key pair.

A SSL certificate contains a RSA key pair. You can generate a RSA key pair by running:

```
%OBSR_HOME%\java\bin\keytool -genkey -alias tomcat -keyalg
RSA -keysize 2048 -keystore %OBSR_HOME%\conf\keystore
```

Also, the key password for the alias "tomcat" must be the same as the keystore password. Please simply press the [Enter] key when you are prompted for the key password for tomcat (i.e. Press [Enter] when you see the "key password for <tomcat>" prompt).

Platform	Example
Windows	<i>C:\Program Files\AhsayOBS and AhsayRPS\conf> "C:\Program Files\AhsayOBS and AhsayRPS\java\bin\"keytool -genkey -alias tomcat - keyalg RSA -keysize 2048 -keystore keystore</i>
Linux	<i>[root]# keytool -genkey -alias tomcat -keyalg RSA - keysize 2048 -keystore /Applications/AhsayOBS/conf/keystore</i>

4. Create a local Certificate Signing Request (CSR).

You can create a CSR for your SSL certificate by running:

```
%OBSR_HOME%\java\bin\keytool -certreq -keyalg RSA -alias  
tomcat -file ssl.csr -keystore %OBSR_HOME%\conf\keystore
```

Platform	Example
Windows	<i>C:\Program Files\AhsayOBS and AhsayRPS\conf> "C:\Program Files\AhsayOBS and AhsayRPS\java\bin\"keytool -certreq -keyalg RSA - alias tomcat -keystore keystore</i>
Linux	<i>[root]# \$OBSR_HOME/java/bin/keytool -certreq - keyalg RSA -alias tomcat -keystore \$OBSR_HOME/conf/keystore</i>

5. Submit the CSR file to a trusted CA of your choice.

6. Import signed SSL certificate from CA back to the keystore from which the CSR was generated by:

```
%OBSR_HOME%\java\bin\keytool -import -alias tomcat -  
trustcacerts -file ssl.crt -keystore  
%OBSR_HOME%\conf\keystore
```

Platform	Example
Windows	<i>C:\Program Files\AhsayOBS and AhsayRPS\conf> "C:\Program Files\AhsayOBS and AhsayRPS\java\bin\"keytool -import -alias tomcat - trustcacerts -file ssl.crt -keystore %OBSR_HOME%\conf\keystore</i>
Linux	<i>[root]# \$OBSR_HOME/java/bin/keytool -list -alias tomcat -keystore \$OBSR_HOME/conf/keystore</i>

If you are getting the "keytool error: java.lang.Exception: Failed to establish chain from reply" message when importing the SSL certificate file from CA, please try double-clicking the ssl.crt file on Windows to view all intermediate certificates being used to sign your certificate and import all intermediate certificates (downloadable from your CA) into your keystore file before importing your SSL certificate.

7. Check if you have installed the SSL certificate correctly by:

```
%OBSR_HOME%\java\bin\keytool -list -alias tomcat -keystore
%OBSR_HOME%\conf\keystore
```

Platform	Example
Windows	<i>C:\Program Files\AhsayOBS and AhsayRPS\conf>"C:\Program Files\AhsayOBS and AhsayRPS\java\bin"keytool -list -alias tomcat -keystore keystore</i>
Linux	<i>[root]# \$OBSR_HOME/java/bin/keytool -list -alias tomcat -keystore \$OBSR_HOME/conf.keystore</i>

Sample Output:

```
Tomcat, 2003/6/13, keyEntry, Certificate fingerprint (MD5):
xx:xx:xx:xx:xx:xx:xx:xx:xx:xx:xx:xx
```

Please make sure that you are getting the type "keyEntry" instead of "trustedCertEntry" from the output above. If you are getting "trustedCertEntry", the most likely cause of this is that you are NOT importing the SSL certificate back into the same keystore from which the CSR was generated. The only solution to this is to find this keystore file and import the certificate(s) to the keystore file again. If you can't find this file, please repeat the instructions in this section from step 1 and try again.

* When asked for your "first and last name" during the key generation, please specify the domain that you will be using this certificate for. Please refer to the following example:

Full Example
<pre>C:\Program Files\AhsayOBS and AhsayRPS\conf> "C:\Program Files\AhsayOBS and AhsayRPS\java\bin"keytool -genkey -alias tomcat -keyalg RSA -keystore keystore Enter keystore password: changeit What is your first and last name? [unknown]: www.secure-company.com What is the name of your organizational unit? [unknown]: NOT SECURE What is the name of your organization? [unknown]: NOT SECURE What is the name of your City or Locality? [unknown]: NOT SECURE What is the name of your State or Province? [unknown]: NOT SECURE What is the two-letter country code for this unit? [unknown]: NS Is <CN=www.secure-company.com, OU=NOT SECURE, O=NOT SECURE, L=NOT SECURE, ST=NOT SECURE, C=NS> correct? [no]: yes</pre>

```

Enter key password for <tomcat>
(RETURN if same as keystore password):

C:\Program Files\AhsayOBS and AhsayRPS\conf> "C:\Program
Files\AhsayOBS and AhsayRPS\java\bin\"keytool -certreq -keyalg
RSA - alias tomcat -file certreq.csr -keystore keystore
Enter keystore password: changeit

C:\Program Files\AhsayOBS and AhsayRPS\conf> "C:\Program
Files\AhsayOBS and AhsayRPS\java\bin\"keytool -import -alias
tomcat -keystore keystore -trustcacerts -file ssl.crt
Enter keystore password: changeit
Certificate reply was installed in keystore

C:\Program Files\AhsayOBS and AhsayRPS\conf> "C:\Program
Files\AhsayOBS and AhsayRPS\java\bin\"keytool -list -alias tomcat -
keystore keystore

Tomcat 2003/06/13, keyEntry, Certificate fingerprint (MD5):
XX:XX:XX:XX:XX:XX:XX:XX:XX:XX:XX:XX:XX:XX:XX:XX
    
```

19.2 Enforcing SSL to the web interface

If you want all users to connect to the web interface of AhsayOBS using SSL to enforce secure connection, please do the followings:

1. Open %OBSR_HOME%\webapps\obs\WEB-INF\web.xml
2. Locate the [Enforce SSL] section at the end of "web.xml"

Web.xml
<pre> ... <!-- ===== ----- --> <!-- ===== Enforce SSL ----- --> <!-- == Please uncomment the following section to enforce SSL for the web interface == --> <!-- ===== ----- --> <!-- <security-constraint> <web-resource-collection> <web-resource-name>Automatic SLL Forwarding</web-resource- name> <url-pattern>/jsp/user/*</url-pattern> <url-pattern>/jsp/system/*</url-pattern> </web-resource-collection> </pre>

```
<user-data-constraint>  
  <transport-guarantee>CONFIDENTIAL</transport-guarantee>  
</user-data-constraint>  
</security-constraint>  
-->  
...
```

3. Remove the XML comment tags ("**<!--**" and "**-->**", shown in red and bold above) from "web.xml"
4. Restart AhsayOBS.

Please note that this only enforces SSL when users log onto the web interface of AhsayOBS. It does not enforce backup traffic from AhsayOBM to be SSL.

20 Monitoring System Activities

This chapter describes how you can use the [Manage Log] -> [System Log] page (shown below) to review system and backup activities of AhsayOBS.

20.1 Reviewing System Log

When you click the [Manage Log] -> [System Log] link available at the top menu, the [System Log] panel will appear. It lists all system messages / warnings / errors logged on any particular date by selecting the required date from the drop down list.

No.	Timestamp	Login Name	Owner	Message
651	9:45:59 AM	test001	--	[info][system]Written block to file D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x09\0x7b\0xe0\0x40\2410375348, client path = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x99\0x42\0x26, seq = 1, size = 1536, CRC = -1
652	9:46:01 AM	test001	--	[info][system]Received block of file D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x20\0xd8\0x06\0x5f\3399383223, client path = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x9a\0xba\0x37\0xd0\3961499674, SEQ = 1, current file size = 0, size to write = 480, IExpectedFileSize = 1536, lastUsedFile = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x99\0x42\0x26, bSameFile = false
653	9:46:01 AM	test001	--	[info][system]Creating new file D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0xd8\0x06\0x5f\3399383223, client path = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x9a\0xba\0x37\0xd0\3961499674, SEQ = 1, last used file = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x99\0x42\0x26
654	9:46:01 AM	test001	--	[info][system]Written block to file D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x20\0xd8\0x06\0x5f\3399383223, client path = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x9a\0xba\0x37\0xd0\3961499674, seq = 1, size = 2016, CRC = 1945936326
655	9:46:04 AM	test001	--	[info][system]Received block of file D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x0b\0x7a\0x41\0x41\3611843524, client path = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x4\0xc6, SEQ = 1, current file size = 0, size to write = 0, IExpectedFileSize = 1535, lastUsedFile = , bSameFile = false
656	9:46:04 AM	test001	--	[info][system]Creating new file D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x0b\0x7a\0x41\0x41\3611843524, client path = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x4\0xc6, SEQ = 1, last used file =
657	9:46:04 AM	test001	--	[info][system]Written block to file D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x0b\0x7a\0x41\0x41\3611843524, client path = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x4\0xc6, seq = 1, size = 1536, CRC = -1
658	9:46:07 AM	test001	--	[info][system]Received block of file D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x17\0x4a\0x15\0xc8\1959218759, client path = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x4\0xc6\0x84\0xa9, SEQ = 1, current file size = 0, size to write = 0, IExpectedFileSize = 1535, lastUsedFile = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x4\0xc6, bSameFile = false
659	9:46:07 AM	test001	--	[info][system]Creating new file D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x17\0x4a\0x15\0xc8\1959218759, client path = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x4\0xc6\0x84\0xa9, SEQ = 1, last used file = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x4\0xc6
660	9:46:07 AM	test001	--	[info][system]Written block to file D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x17\0x4a\0x15\0xc8\1959218759, client path = D:\Test-Data\obs2\User\test001\Files\1254731963006\Current\0x4\0xc6\0x84\0xa9, seq = 1, size = 1536, CRC = -1

Key	Description
Date	The date when all messages were logged.
Rows/Page	The number of rows to display per page.
Timestamp	The time when the message was logged.
Login Name	The login name of the related user.
Owner	The owner of this user.
Message	The system log message.

20.2 Reviewing Backup Log

When you click the [Manage Log] -> [Backup Log] link available at the top menu, the [Backup Log] panel will appear. It lists all backup jobs run on a particular date. You can review the backup jobs run on any particular date by selecting the required date from the drop down list.

No.	Backup Time	Login Name > Backup Set > Job Number	Owner	Client Version	Upload Size	Job Status
1	02/10 03:27PM - 02/10 03:28PM	OBM User1 > BackupSet-0 > 2009-10-02 (15:27)	--	6.0.0.0	8.11M	OK
2	02/10 04:12PM - 02/10 04:13PM	OBM User1 > BackupSet-0 > 2009-10-02 (16:12)	--	6.0.0.0	114k	OK
3	02/10 04:13PM - 02/10 04:13PM	OBM User1 > BackupSet-0 > 2009-10-02 (16:13)	--	6.0.0.0	50k	OK
4	02/10 04:13PM - 02/10 04:13PM	OBM User1 > BackupSet-0 > 2009-10-02 (16:13)	--	6.0.0.0	52k	OK
5	02/10 04:13PM - 02/10 04:13PM	OBM User1 > BackupSet-0 > 2009-10-02 (16:13)	--	6.0.0.0	55k	OK
6	02/10 05:23PM - 02/10 05:23PM	OBM User1 > BackupSet-0 > 2009-10-02 (17:23)	--	6.0.0.0	0	User interrupted

Key	Description
Date	The date when all backup jobs listed below were run.
Backup Time	Start and end time of this backup job.
Login Name > Backup Set > Job Number	Backup Account that ran this backup job.
Owner	Owner of this backup user.
Client Version	The AhsayOBM/AhsayACB version number that this backup user is using.
Upload Size	Size of backup data uploaded.
Status	Overall status of the backup job.

20.3 Reviewing Restored File Log

When you click the [Manage Log] -> [Restored File] link available at the top menu, the [Restore Log] panel will appear. It lists all online file restoration activities logged within a date. You can review online file restoration activities recorded on any particular date by selecting the required date from the drop down list.

No.	Restore Time	Login Name	Owner	Size	IP
1	2009/09/24 10:59:07AM - 2009/09/24 10:59:09AM	DMTestCase3	--	80k	192.168.6.185
2	2009/09/24 11:00:48AM - 2009/09/24 11:00:49AM	DMTestCase3	--	46k	192.168.6.185
3	2009/09/24 11:00:03AM - 2009/09/24 11:00:03AM	DMTestCase3	--	38k	192.168.6.185
4	2009/09/24 11:02:48AM - 2009/09/24 11:02:48AM	DMTestCase3	--	56k	192.168.6.185
5	2009/09/24 11:05:52AM - 2009/09/24 11:06:12AM	DMTestCase3	--	382k	192.168.6.185
6	2009/09/24 11:05:34AM - 2009/09/24 11:05:34AM	DMTestCase3	--	65k	192.168.6.185
7	2009/09/24 11:08:53AM - 2009/09/24 11:08:56AM	DMTestCase3	--	92k	192.168.6.185
8	2009/09/24 11:13:23AM - 2009/09/24 11:13:25AM	DMTestCase3	--	195k	192.168.6.185
9	2009/09/24 11:19:57AM - 2009/09/24 11:20:05AM	DMTestCase3	--	192k	192.168.6.185
10	2009/09/24 11:19:26AM - 2009/09/24 11:19:33AM	DMTestCase3	--	125k	192.168.6.185
11	2009/09/24 11:19:14AM - 2009/09/24 11:19:16AM	DMTestCase3	--	80k	192.168.6.185
12	2009/09/24 11:20:28AM - 2009/09/24 11:20:39AM	DMTestCase3	--	366k	192.168.6.185
13	2009/09/24 11:20:12AM - 2009/09/24 11:20:20AM	DMTestCase3	--	274k	192.168.6.185
14	2009/09/24 11:27:06AM - 2009/09/24 11:27:17AM	DMTestCase3	--	274k	192.168.6.185
15	2009/09/24 11:34:57AM - 2009/09/24 11:34:59AM	DMTestCase3	--	91k	192.168.6.185
16	2009/09/24 11:37:10AM - 2009/09/24 11:37:12AM	DMTestCase3	--	195k	192.168.6.185
17	2009/09/24 02:48:53PM - 2009/09/24 02:49:07PM	DMTestCase3	--	255k	192.168.6.185
18	2009/09/24 02:48:22PM - 2009/09/24 02:48:36PM	DMTestCase3	--	256k	192.168.6.185
19	2009/09/24 02:50:45PM - 2009/09/24 02:50:59PM	DMTestCase3	--	255k	192.168.6.185
20	2009/09/24 02:50:10PM - 2009/09/24 02:50:10PM	DMTestCase3	--	83k	192.168.6.185
21	2009/09/24 02:51:59PM - 2009/09/24 02:52:00PM	DMTestCase3	--	83k	192.168.6.185
22	2009/09/24 03:17:20PM - 2009/09/24 03:17:21PM	DMTestCase3	--	83k	192.168.6.187
23	2009/09/24 03:19:56PM - 2009/09/24 03:28:14PM	DMTestCase3	--	83k	192.168.6.187
24	2009/09/24 03:31:30PM - 2009/09/24 03:31:30PM	DMTestCase3	--	0	192.168.6.187
25	2009/09/24 03:33:47PM - 2009/09/24 03:33:47PM	DMTestCase3	--	0	192.168.6.187
26	2009/09/24 03:33:02PM - 2009/09/24 03:33:02PM	DMTestCase3	--	0	192.168.6.187
27	2009/09/24 05:48:25PM - 2009/09/24 05:48:29PM	alan	--	80k	192.168.6.184

Key	Description
Date	The date when all online file restoration were recorded.
Restore Time	Start and end time of file restoration activities.
Login Name	Backup account restoring files from the server.
Owner	The owner of this backup user.
Size	Total backup data restored from the server.
IP	IP address to where backup data were restored.

20.4 Reviewing Backup Error log

When you click the [Manage Log] -> [Backup Error] link available at the top menu, the [Backup Error] panel will appear. It lists all backup errors or warning logged within a date. You can review backup errors or warnings logged on any particular date by selecting the required date from the dropdown list.

The screenshot shows the Ahsay Offsite Backup Server interface. At the top, there is a navigation bar with links: Manage System, Manage Log, Manage User, Manage Group Policy, Manage System User, Administrator's Guide, and Select Language. Below this is a secondary navigation bar with links: System Log, Backup Job, Restored File, Backup Error, Replication Log, and Advertisement Log. A 'Logout' button is also present.

The main content area features a date selector set to '2009-09-16' and a 'Rows/Page: 50' dropdown. Below the date selector is a table with the following data:

No.	Timestamp	Login Name	Owner	Errors/Warning
1	03:41:42PM	DMTestCase	--	Backup source "E:\Development Testcases\Delta Merge TestCase\Create Delta\OF+OI\All zero Testcase.txt" does not exist !
2	03:41:44PM	DMTestCase	--	Backup completed with warning(s)
3	05:06:06PM	DMTestCase2	--	BS_DELTA_MERGE_NOT_ENABLED
4	05:06:38PM	DMTestCase2	--	Backup completed with warning(s)


Below the table, there are several sections for getting started with different Ahsay components: Ahsay Online Backup Manager (AhsayOBM), Ahsay Offsite Backup Server (AhsayOBS), Ahsay A-Click Backup (AhsayACB), and Ahsay Replication Server (AhsayRPS). There are also links for 'Getting Started with AhsayOBM', 'Getting Started with AhsayACB', 'Key Features', 'Documentations', 'System Management', and 'Contact us'.

At the bottom of the page, there is a footer area with a text box containing instructions to edit the 'INSTALL_FOLDER' file to customize the company logo and software names. Below this are two placeholder boxes for 'Your Company Logo'.

Key	Description
Date	The date when all messages were logged.
Timestamp	The time when this message was logged.
Login Name	Backup account raising this error or warning.
Owner	The owner of this backup user.
Errors/Warnings	Details of the error or warning recorded.

20.5 Reviewing Replication Log

When you click [Manage Log] -> [Replication Log] link available at the top menu, the [Replication Log] panel will appear. It lists all replication activities logged within a date. You can review the replication activities recorded on any particular date by selecting the required date from the drop down list.



Key	Description
Date	The date when the replication activities were logged.
Rows/Page	The number of rows to display per page.
Timestamp	The time when the replication was displayed.
Message	Details of the activities.

20.6 Reviewing Advertisement Log

When you click the [Manage Log] -> [Advertisement Log] link available at the top menu, the [Advertisement Log] panel will appear. It lists all the advertisements displayed by AhsayOBM/AhsayACB clients for a particular date. You can review displayed adverts on any particular date by selecting the required date from the dropdown list.

No.	Timestamp	Name	Type	User Name	Owner	Remote IP	URL
1	10:14:05 AM	2	IMP	test001	--	127.0.0.1	www.google.com
2	10:14:15 AM	3	IMP	test001	--	127.0.0.1	www.cnn.com
3	10:14:26 AM	AHSAY	IMP	test001	--	127.0.0.1	www.ahsay.com
4	10:14:36 AM	1	IMP	test001	--	127.0.0.1	www.ahsay.com
5	10:14:43 AM	2	IMP	test001	--	127.0.0.1	www.google.com
6	10:14:54 AM	3	IMP	test001	--	127.0.0.1	www.cnn.com
7	10:15:04 AM	AHSAY	IMP	test001	--	127.0.0.1	www.ahsay.com
8	10:15:15 AM	1	IMP	test001	--	127.0.0.1	www.ahsay.com
9	10:15:22 AM	2	IMP	test001	--	127.0.0.1	www.google.com
10	10:15:33 AM	3	IMP	test001	--	127.0.0.1	www.cnn.com
11	10:15:44 AM	AHSAY	IMP	test001	--	127.0.0.1	www.ahsay.com
12	10:15:55 AM	1	IMP	test001	--	127.0.0.1	www.ahsay.com
13	10:16:02 AM	2	IMP	test001	--	127.0.0.1	www.google.com
14	10:16:13 AM	3	IMP	test001	--	127.0.0.1	www.cnn.com
15	10:16:23 AM	AHSAY	IMP	test001	--	127.0.0.1	www.ahsay.com
16	10:16:34 AM	1	IMP	test001	--	127.0.0.1	www.ahsay.com
17	10:16:41 AM	2	IMP	test001	--	127.0.0.1	www.google.com
18	10:16:52 AM	3	IMP	test001	--	127.0.0.1	www.cnn.com
19	10:17:03 AM	AHSAY	IMP	test001	--	127.0.0.1	www.ahsay.com

Key	Description
Date	The date when the advertisements listed below were displayed.
Rows/Page	The number of rows to display per page.
Timestamp	The time when the advertisement was displayed.
Name	The name of the advertisement.
Type	Advertisement display types: <ul style="list-style-type: none"> IMP - Impression, this advertisement was displayed. HIT - Hit, this advertisement was displayed and the user clicked the advert to go to the target web page.
User Name	The user account name of the AhsayOBM/AhsayACB client.
Owner	The owner of this backup user.
Remote IP	The remote IP address of the AhsayOBM/AhsayACB client.
URL	The target URL associated with this ad.

21 Branding AhsayOBM & AhsayACB

21.1 Customization Portal

The Ahsay Customization Portal (<http://partners.ahsay.com/>) allows you to do the followings:

1. Building custom installers for the followings Ahsay products:
 - iv. AhsayOBS and AhsayRPS
 - v. AhsayACB and AhsayOBM
 - vi. AhsayNCU (For AhsayOBS v5.5 or below)
2. Set the vendor name, support email and URL to your own values.
3. Put your own company logo and other images into the software.
4. Set the default backup server hostname, TCP port number and protocol (HTTP/HTTPS) to your own values.
5. Hide/Show encrypting key checkbox in AhsayACB/AhsayOBM.
6. Hide/Show language selection list in AhsayACB/AhsayOBM.
7. Hide/Show the backup server URL textbox.
8. Set the default language for AhsayACB/AhsayOBM.
9. Enable/Disable languages for AhsayACB/AhsayOBM.
10. Enable/Disable user account profile update from AhsayACB/AhsayOBM.
11. Customize the terms of use statements shown in the installer of AhsayACB/AhsayOBM.

Once you have made all the customization you want, you can download a customized version of AhsayOBSR / AhsayACB / AhsayOBM / AhsayNCU from the download page (shown below) of the customization portal.

Please refer to the [Ahsay Customization Portal User Guide](#) from the Ahsay Customization Portal for more information.

22 Branding AhsayOBS

This chapter describes how you can customize AhsayOBS to make it look the way you want it to be.

22.1 Welcome Page

If you would like to use your own welcome page on the backup server, simply replace the default welcome page, %OBSR_HOME%\webapps\ROOT\index.html, with your own welcome page.

22.2 Different welcome pages for different domains

If you want to show different welcome pages for requests to different domain names, please do the followings:

1. Rename %OBSR_HOME%\webapps\ROOT\index.html to %OBSR_HOME%\webapps\ROOT\index_defaultDomain.html
2. Create %OBSR_HOME%\webapps\ROOT\index.jsp with the following content. Suppose you have 4 domains in total. If you want requests to AhsayOBS using the domain name "domain2.com" to see "index_Domain2.html" and request to AhsayOBS using the domain name "domain3.com" to see "index_Domain3.html", you should put the highlighted code below.

%OBSR_HOME%\webapps\ROOT\index.jsp

```
<%@ page language="java" %>
<%--

If you want to redirect request from different domains to different
index pages, please modify the "domain to URL mapping" defined by
the
String array declaration below to define your own mapping.

--%>
<%
String sURL = "index_defaultDomain.html";
String sRequestURL =
request.getRequestURL().toString().toLowerCase();
String[] asMap = {
    "domain2.com", "index_Domain2.html",
    "domain3.com", "index_Domain3.html",
};
for(int i=0; asMap!=null && i<asMap.length; i+=2) {
    String sDomain = asMap[i].toLowerCase();
    if(sRequestURL.indexOf(sDomain)!=-1) {
        sURL=asMap[i+1];
    }
}
```

```


break;
    }
}
response.sendRedirect(sURL);
%>

```

Please note that you need to create both the "index_Domain2.html" and "index_Domain3.html" yourself and place it in the %OBSR_HOME%\webapps\ROOT directory.

22.3 Customizing the company logo displayed

Two different logos are displayed on the bottom left hand corner and bottom right hand corner of every page.



You can customize the logos shown on the bottom left hand corner and the bottom right hand corner of every page by:

1. Go to %OBSR_HOME%\webapps\obs\logo
2. To display your image at the bottom left hand corner of every page, simply save your image as "default.small.left.gif" in the directory above.
3. To display your image at the bottom right hand corner of every page, simply save your image as "default.small.right.gif" in the directory above.

4. If you do not want to display any images at these locations, just rename "empty.gif" to "default.small.left.gif" or "default.small.right.gif".

Different logos for different domain names

If you are mapping both domain www.company-A.com and domain www.company-B.com to the IP address of the AhsayOBS and you want to display different logos when users are browsing the web pages using different domain names, you can achieve that by the use of Reseller Panel feature:

1. Logon to AhsayOBS with the system admin role system user.
2. Go to [Manage System User] -> [Add System User] to create two sub-admin role system user account, 1 for www.company-A.com and www.company-B.com.
3. Logoff from AhsayOBS.
4. Logon with the Sub-Admin role system account of www.company-A.com.
5. Go to [Manage System User] -> [My Profile] page to download the default customization file by clicking on the "default customization file" link.
6. Unzip the zip file to a temporary directory and go to "gif" directory inside.
7. Replace small.right.gif and small.left.gif with the company logo of www.company-A.com.
8. Zip all the customized files with the name custom.zip.
9. On the [My Profile] page, check the [Customize Interface] checkbox.
10. Upload the custom.zip to the AhsayOBS by clicking on the [Browse] button and select the custom.zip file in the dialog.
11. Click the [Update] button to apply the change. This change should be applied to the AhsayOBS immediately.
12. Repeat the Step 4 - 11 for www.company-B.com.

22.4 Customizing the Look and Feel of the web interface

The Look and Feel (e.g. font size and color) of the web interface of AhsayOBS is defined by a set of rules defined in a cascade style sheet. If you want to customize the Look and Feel of the web interface to fully integrate AhsayOBS into your website, you can do the followings:

1. Open %OBSR_HOME%\webapps\obs\jsp\lib\jsp_*.css (e.g. en=English, fr=French, cs=Czech, da=Danish, nl=Dutch, de=German, es=Spanish, sv=Swedish, zh_TW=Traditional_Chinese, zh_CN=Simplified_Chinese etc).
2. Make the changes to the cascade style sheet file to what you would like to see.

For example, if you want to change the English user menu bar from yellowish color (#FFCC00) to red color. Please do the followings:

Extract of jsp_en.css (Original)

```
...
/* menu bar - background color; text color, weight */
.usermenu_menubar {
    background-color: #FFCC00;
    color: #000000
    font-weight: normal
}
...
```

Extract of jsp_en.css (Updated)

```
...
/* menu bar - background color; text color, weight */
.usermenu_menubar {
    background-color: red;
    color: #000000
    font-weight: normal
}
...
```

3. Restart your browser to see the changes.

22.5 Customizing all text of the web interface

All text displayed on the web interface of AhsayOBS is stored in properties files. If you want to modify any of the text information on the web interface, please do the followings:

1. Connect to Ahsay Customization Portal.
2. Go to [Step 1 – Customize Properties].
3. Select “OBS – Web Interface” on the customize properties page.
4. Modify the entries that you want to customize.
5. Press the [Generate and Download All Properties] button to download the customized properties files.
6. Unzip the file downloaded in previous step.
7. Copy the generated `jsp_*.properties` files found in `properties.zip\custom-obsr\app\common\webapps\obs\WEB-INF\classes` to `%OBSR_HOME%\webapps\obs\WEB-INF\classes`.
8. Restart AhsayOBS backup services to apply the changes.

22.6 Customizing email reports

The instructions of customizing all text in all outgoing email reports is the same as the instruction of customizing all text displayed on the web interface. Simply do this:

1. Go to [Ahsay Customization Portal](#) (AhsayACP).
2. Click on [Step 1. Customize Properties].
3. Select [OBS – Web Interface] from the group drop down menu.
4. Modify the “`jsp.report.*`” entries that you would like to cusotmize.
5. Press the [Generate and Download All Properties] button to download the customized properties files.
6. Unzip the file downloaded in previous step.
7. Copy the generated `jsp_*.properties` files found in `properties.zip\custom-obs\app\common\webapps\obs\WEB-INF\classes` to `%OBSR_HOME%\webapps\obs\WEB-INF\classes`
8. Restart AhsayOBS backup services to apply the changes.

If you are interested in displaying your own logo in all out-going email reports, simply replace `%OBSR_HOME%\webapps\obs\logo\default.large.gif`

with your own logo. All email reports sent after you have made the changes will carry your customized logo.

22.7 Localizing the software

It is currently possible to have AhsayOBS localized to another language without the assistance of your development team. The list of supported languages is attached in the appendix section.

If you would like to have AhsayOBS available in languages other than those currently supported, please feel free to contact us to discuss possible arrangement.

23 Advanced Configuration

The default installation of AhsayOBS setup a typical environment to run your backup server but it is still possible that the default setting does not fit well into your environment. This chapter describes all supported customizations that you can do to the software to fulfill your special needs.

23.1 Listening to non-standard TCP/IP Port

If you like to run your own web server, or some other services using port 80 and 443, on your backup server, you can change the listening TCP/IP port of AhsayOBS from port 80 and 443 to some other port numbers by:

1. Open %OBSR_HOME%\conf\server.xml

Server.xml
<pre> <Server port="8014" shutdown="SHUTDOWN" debug="0"> <Service name="Tomcat-Standalone"> <!-- Define a non-SSL HTTP/1.1 Connector on port 80 --> <Connector className="org.apache.coyote.tomcat5.CoyoteConnector" address="0.0.0.0" port="80" maxHttpHeaderSize="8192" maxKeepAliveRequests="1" maxThreads="1000" minSpareThreads="25" maxSpareThreads="100" enableLookups="false" redirectPort="443" bufferSize="32768" acceptCount="1000" connectionTimeout="600000" disableUploadTimeout="true"/> <!-- Define a SSL HTTP/1.1 Connector on port 443 --> <Connector className="org.apache.coyote.tomcat5.CoyoteConnector" address="0.0.0.0" port="443" maxHttpHeaderSize="8192" maxKeepAliveRequests="1" maxThreads="1000" minSpareThreads="25" maxSpareThreads="100" enableLookups="false" disableUploadTimeout="true" acceptCount="1000" bufferSize="32768" scheme="https" secure="true" keystoreFile="conf/keystore" keystorePass="changeit" clientAuth="false" sslProtocol="TLS" connectionTimeout="600000"/> </pre>

2. Change the [port] values (shown in red and bold above) to the preferred port numbers. For example, to change the HTTP port

from port 80 to 8080 and HTTPS port from port 443 to port 8443, please do the followings:

port="80" -> port="8080"

redirectPort="443" -> redirectPort="8443"

port="443" -> port "8443"

3. Restart AhsayOBS.
4. Logon the System Management Console.

23.2 Listening to a single IP address

If the backup server has more than one network interface installed or has more than one IP address bind to a single network interface, you can configure AhsayOBS to use only a single IP address for backup services (by default the TCP port of all IP addresses available within the system are used and open). This has the benefits of sparing other IP addresses for other applications, e.g. Apache Web Server or Microsoft Internet Information Server (IIS). To do so,

1. Open %OBSR_HOME%\conf\server.xml

Server.xml
<pre> <Server port="8014" shutdown="SHUTDOWN" debug="0"> <Service name="Tomcat-Standalone"> <!-- Define a non-SSL HTTP/1.1 Connector on port 80 --> <Connector className="org.apache.coyote.tomcat5.CoyoteConnector" address="0.0.0.0" port="80" maxHttpHeaderSize="8192" maxKeepAliveRequests="1" maxThreads="1000" minSpareThreads="25" maxSpareThreads="100" enableLookups="false" redirectPort="443" bufferSize="32768" acceptCount="1000" connectionTimeout="60000" disableUploadTimeout="true"/> <!-- Define a SSL HTTP/1.1 Connector on port 443 --> <Connector className="org.apache.coyote.tomcat5.CoyoteConnector" address="0.0.0.0" port="443" maxHttpHeaderSize="8192" maxKeepAliveRequests="1" maxThreads="1000" minSpareThreads="25" maxSpareThreads="100" enableLookups="false" disableUploadTimeout="true" acceptCount="1000" bufferSize="32768" scheme="https" secure="true" keystoreFile="conf/keystore" keystorePass="changeit" </pre>

```

clientAuth="false"
connectionTimeout="600000"/>
sslProtocol="TLS"

```

2. Change the [address] values (shown in red and bold above) to the IP addresses that are to be used for AhsayOBS. For example, to use only the IP address, 192.168.1.1, for backup services, change address values from "0.0.0.0" (means all available IP addresses) to "192.168.1.1".

address="0.0.0.0" -> address="192.168.1.1"

3. Restart AhsayOBS.

If you are going to use IIS along with AhsayOBS on different IP addresses as mentioned here, please make sure that you have configured IIS to spare the IP address configured above to be used by AhsayOBS (by default IIS will use all the IP addresses available). Failing to do so will result in failing to start both IIS and AhsayOBS at the same time.

23.3 Restricting access to system page by IP address

For better security, you can restrict access to the system administration console by IP addresses. To do so, please do the followings:

1. Open %OBSR_HOME%\webapps\obs\WEB-INF\web.xml.
2. Locate the SystemConsole filter under "filter" section near the beginning of "web.xml".

Web.xml

```

...
<filter>
  <filter-name>SystemConsole</filter-name>
  <filter-class>com.ahsay.obs.www.IPFilter</filter-class>
  <init-param>
    <param-name>Range1</param-name>
    <param-value>localhost</param-value>
  </init-param>
  <init-param>
    <param-name>Range2</param-name>
    <param-value>0.0.0.0-255.255.255.255</param-value>
  </init-param>
</filter>
...

```

3. Change the "Range2" parameter value from "127.0.0.1-127.0.0.1" (shown in red and bold above) to a range of IP addresses from where access to the system administration console is allowed.

For example, changing [Range2] value from "127.0.0.1-127.0.0.1" to "192.168.1.1-192.168.1.255" to allow the 192.168.1.x network to invoke the APIs.

Web.xml (Updated)

```

...
<filter>
  <filter-name>SystemConsole</filter-name>
  <filter-class>com.ahsay.obs.www.IPFilter</filter-class>
  <init-param>
    <param-name>Range1</param-name>
    <param-value>localhost</param-value>
  </init-param>
  <init-param>
    <param-name>Range2</param-name>
    <param-value>192.168.1.1-192.168.1.255</param-value>
  </init-param>
</filter>
...

```

Please note that you can configure more than one IP range by adding additional init parameters (i.e. "Range3", "Range4" and so do) to the filter XML tag. For example:

```

<filter>
  <filter-name>SystemConsole</filter-name>
  <filter-class>com.ahsay.obs.www.IPFilter</filter-class>
  <init-param>
    <param-name>Range1</param-name>
    <param-value>localhost</param-value>
  </init-param>
  <init-param>
    <param-name>Range2</param-name>
    <param-value>192.168.1.1-192.168.1.255</param-value>
  </init-param>
  <init-param>
    <param-name>Range3</param-name>
    <param-value>192.168.2.1-192.168.2.255</param-value>
  </init-param>
</filter>

```

4. Restart AhsayOBS.

24 External API References

AhsayOBS contains a set of APIs (Application Programming Interface), which allows you to integrate external applications (e.g. billing system or automated registration system) with AhsayOBS. This chapter describes what APIs are available and how you can invoke different APIs.

You can find more information on processing XML using JAVA at <http://java.sun.com/xml>.

24.1 Overview

AhsayOBS APIs can be invoked by using standard HTTP request method (i.e. either POST or GET). For example, to invoke the [Remove User] API, simply use any programming /scripting languages of your choice to invoke: http://BACKUP_SERVER/obs/api/RemoveUser.do?SysUser=system&SysPwd=system&LoginName=test to delete user "test".

URL encoding must be applied to all non-alphanumeric parameters when submitting the API requests as specified in the HTTP protocol specification. For example, a value of "GMT-08:00 (PSL)" must submit to AhsayOBS as "GMT%2d08%3a00+%28PST%29" via external API.

24.2 Limitations

There are some limitations for using API:

- API supports only System Administrator account (i.e. system user specified in %OBSR_HOME%\conf\obs.xml). Therefore, it is required to use System Administrator account for making any API call.
- Currently, API only supports modifications related to backup users or backup user groups.

24.3 IP Restrictions

To avoid AhsayOBS's APIs from being exploited by hackers from an unauthorized network, AhsayOBS, by default, accepts and handles only the API requests originating from the same local machine. To loosen this restriction, please do the followings:

1. Open %OBSR_HOME%\webapps\obs\WEB-INF\web.xml.
2. Locate the LocalHostOnly filter under the "filter" section near the beginning of "web.xml".

- Change the [Range1] parameter value from "127.0.0.1-127.0.0.1" (shown in red and bold above) to another range of IP addresses from where APIs can be invoked.

```

web.xml
...
<filter>
  <filter-name>LocalhostOnly</filter-name>
  <filter-class>com.ahsay.obs.www.IPFilter</filter-class>
  <init-param>
    <param-name>Range1</param-name>
    <param-value>localhost</param-value>
  </init-param>
  <init-param>
    <param-name>Range2</param-name>
    <param-value>127.0.0.1-127.0.0.1</param-value>
  </init-param>
</filter>
...

```

For example, changing [Range1] value from "127.0.0.1-127.0.0.1" to "192.168.1.1-192.168.1.255" to allow the 192.168.1.x network to invoke the APIs.

```

web.xml (Updated)
...
<filter>
  <filter-name>LocalhostOnly</filter-name>
  <filter-class>com.ahsay.obs.www.IPFilter</filter-class>
  <init-param>
    <param-name>Range1</param-name>
    <param-value>localhost</param-value>
  </init-param>
  <init-param>
    <param-name>Range2</param-name>
    <param-value>192.168.1.1-192.168.1.255</param-value>
  </init-param>
</filter>
...

```

Please note that you can configure more than two IP ranges by adding additional init parameters (i.e. "Range3", "Range4" and so on) to the filter XML tag. For example:

```

<filter>
  <filter-name>LocalhostOnly</filter-name>
  <filter-class>com.ahsay.obs.www.IPFilter</filter-class>
  <init-param>
    <param-name>Range1</param-name>
    <param-value>localhost</param-value>
  </init-param>

```

```
<init-param>
  <param-name>Range2</param-name>
  <param-value>192.168.1.1-192.168.1.255</param-value>
</init-param>
<init-param>
  <param-name>Range3</param-name>
  <param-value>192.168.2.1-192.168.2.255</param-value>
</init-param>
</filter>
```

4. Restart AhsayOBS.

24.4 User Authorization

The following table describes all information required to invoke the [Auth User] API to check whether an existing user is authorized.

URL:			
http://BACKUP_SERVER/obs/api/AuthUser.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	Login name of the user	
Password	String	Login password of the user	
Return Value:			
If successful, returns <OK/>			
If there is an error, returns <err>%ERROR_MESSAGE%</err>			
i. Login name does not exist or incorrect login name			
<i><err>[UserCacheManager.NoSuchUserExpt] User '%USER_NAME%' not found.</err></i>			
ii. Incorrect user password specified			
<i><err>[UserCacheManager.PasswordIncorrectExpt] Incorrect password for user '%USER_NAME%'.</err></i>			
iii. Incorrect system username and or password			
<i><err>Incorrect system username/password</err></i>			
Example:			
To verify the a user with user name "test" and password "abc"			
http://BACKUP_SERVER/obs/api/AuthUser.do?SysUser=system&SysPwd=system&LoginName=test&Password=abc			

24.5 Adding User

The following table describes all information required to invoke the [Add User] API to add a new user to AhsayOBS. For using this API with AhsayRDR, new backup user will be added to first user home defined in AhsayOBS user homes settings by default.

URL:			
http://BACKUP_SERVER/obs/api/AddUser.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	New user's login Name	
Password	String	New user's password	
Alias	String	New user's alias	
Language	String	New user's language	
Type	String	New user's type	
Adgroup	String	Advertisement group. { ALL NONE <ADGROUP_ID> }	
Quota	Number	New user's quota, e.g. 104857600 (for 100MB)	
UserHome	String	User Home to use for the new user (must be one of the configured user home), e.g. C:\Program Files\AhsayOBS and AhsayRPS\user	
Enable MSSQL	Boolean	Whether to enable Microsoft SQL Server module for the new user. { Y N }	
EnableMSExchange	Boolean	Whether to enable Microsoft Exchange Server module for the new user. { Y N }	
EnableOracle	Boolean	Whether to enable Oracle module for the new user. { Y N }	
EnableLotusNotes	Boolean	Whether to enable Lotus Notes module for the new user. { Y N }	
EnableLotusDomino	Boolean	Whether to enable Lotus Domino module for the new user. { Y N }	
EnableMySQL	Boolean	Whether to enable MySQL module for the new user. { Y N }	
EnableInFileDelta	Boolean	Whether to enable In-File Delta Module for the new user. { Y N }	
EnableShadowCopy	Boolean	Whether to enable ShadowCopy module for the new user. { Y N }	
EnableExchangeMail box	Boolean	Whether to enable Brick Level Microsoft Exchange module for the new user. { Y N }	
EnableCDP	Boolean	Whether to enable Continuous Data	

			Protection (CDP) module for the new user. { Y N }
EnableShadowProtectBareMetal	Boolean		Whether to enable StorageCraft Shadow Protect module for the new user. { Y N } (added since v5.5.5.0)
EnableWinServer2008BareMetal	Boolean		Whether to enable Windows Server 2008 bare metal module for the new user. { Y N } (added since v5.5.5.0)
ExchangeMailboxQuota	Number		The number of Microsoft Exchange mailboxes allowed for the new user
EnableNASClient	Boolean		Whether to enable AhsayOBM JVM Royalty for the new user. { Y N }
EnableDeltaMerge	Boolean		Whether to enable Enable Delta Merge module for the new user. { Y N } (added since v6.3.0.0)
EnableMsVm	Boolean		Whether to enable HyperV module for the new user. { Y N } (added since v6.3.0.0)
MsVmQuota	Number		The number of HyperV Guest VM allowed for the new user (added since v6.3.0.0)
EnableVMware	Boolean		Whether to enable VMware module for the new user. { Y N } (added since v6.3.0.0)
VMwareQuota	Number		The number of VMware Guest VM allowed for the new user (added since v6.3.0.0)
Contact	String		Extra contact name. (Max: 9) Notes: There can be more than one extra name added, extra contact name must be in pair with extra email
Email	String		Extra contact e-mail. (Max: 9) Notes: There can be more than one extra email added. Extra contact email must be in pair with extra contact name.
Timezone	String		New User's time zone setting. It has to be either one of the following entries: Please make sure the parameter is properly URL encoded. E.g. GMT-08:00 (PST) => GMT%2d08%3a00+%28PST%29
Bandwidth	Number		0 = Unlimited Bandwidth
Notes	String		
Email	String		New user's contact email
SendWelcomeMail	Boolean		{ Y N }
SuspendPaidUser	Boolean		{ Y N }
SuspendPaidUserData	String		A date in yyyy-MM-dd format

Replicated	Boolean	Whether to replicate the new user. { Y N }
Return Value:		
If successful, returns <OK/> If there is an error, returns <err>%ERROR_MESSAGE%</err>		
Example:		
http://BACKUP_SERVER/obs/api/AddUser.do?SysUser=system&SysPwd=system&LoginName=test&Password=abc&Alias=Testing&Language=en&Email=abc%40abc%2Ecom&Type=PAID&Quota=100000&UserHome=E%3A%5C&EnableMSSQL=Y&EnableMSExchange=Y&EnableOracle=Y&EnableLotusNotes=Y&EnableLotusDomino=Y&EnableMySQL=Y&EnableInFileDelta=Y&EnableShadowCopy=Y&EnableCDP=Y&EnableShadowProtectBareMetal=Y&EnableWinServer2008BareMetal=Y&EnableDeltaMerge=Y&EnableMsVm=Y&MsVmQuota=10&EnableVMware=Y&VMwareQuota=10&Timezone=GMT%2d08%3a00+%28PST%29&Contact1=john&Email1=john%40someDomain%2Ecom&Contact2=paul&Email2=paul%40anotherDomain%2Ecom&EnableExchangeMailbox=Y&ExchangeMailboxQuota=10&ClientType=OBM		

24.6 Modifying User Profile

The following table describes all information required to invoke the [Modify User] API to update a user's profile in an AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/ModifyUser.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	New user's login Name	
Password	String	New user's password	
Alias	String	New user's alias	
Language	String	New user's language Please refer to Appendix A for the list of available languages.	
Type	String	New user's type	
ClientType	String	New user's Client Type	
Adgroup	String	Advertisement group. { ALL NONE <ADGROUP_ID> }	
Quota	Number	New user's quota, e.g. 104857600 (for 100MB)	
UserHome	String	User Home to use for the new user (must be one of the configured user home), e.g. C:\Program Files\AhsayOBS	

			and AhsayRPS\user
Enable MSSQL	Boolean		Whether to enable Microsoft SQL Server module for the new user. { Y N }
EnableMSExchange	Boolean		Whether to enable Microsoft Exchange Server module for the new user. { Y N }
EnableOracle	Boolean		Whether to enable Oracle module for the new user. { Y N }
EnableLotusNotes	Boolean		Whether to enable Lotus Notes module for the new user. { Y N }
EnableLotusDomino	Boolean		Whether to enable Lotus Domino module for the new user. { Y N }
EnableMySQL	Boolean		Whether to enable MySQL module for the new user. { Y N }
EnableInFileDelta	Boolean		Whether to enable In-File Delta Module for the new user. { Y N }
EnableShadowCopy	Boolean		Whether to enable ShadowCopy module for the new user. { Y N }
EnableExchangeMail box	Boolean		Whether to enable Brick Level Microsoft Exchange module for the new user. { Y N }
EnableCDP	Boolean		Whether to enable Continuous Data Protection (CDP) module for the new user. { Y N }
EnableShadowProtectBareMetal	Boolean		Whether to enable StorageCraft Shadow Protect module for the new user. { Y N } (added since v5.5.5.0)
EnableWinServer2008BareMetal	Boolean		Whether to enable Windows Server 2008 bare metal module for the new user. { Y N } (added since v5.5.5.0)
ExchangeMailboxQuota	Number		The number of Microsoft Exchange mailboxes allowed for the new user
EnableDeltaMerge	Boolean		Whether to enable Enable Delta Merge module for the new user. { Y N } (added since v6.3.0.0)
EnableMsVm	Boolean		Whether to enable HyperV module for the new user. { Y N } (added since v6.3.0.0)
MsVmQuota	Number		The number of HyperV Guest VM allowed for the new user (added since v6.3.0.0)
EnableVMware	Boolean		Whether to enable VMware module for the new user. { Y N } (added since v6.3.0.0)
VMwareQuota	Number		The number of VMware Guest VM allowed for the new user (added since v6.3.0.0)
EnableNASClient	Boolean		Whether to enable AhsayOBM JVM Royalty for the new user. { Y N }
Contact	String		Extra contact name. (Max: 9)

			Notes: There can be more than one extra name added, extra contact name must be in pair with extra email.
Email	String		Extra contact e-mail. (Max: 9) Notes: There can be more than one extra email added, extra contact email must be in pair with extra contact name.
Timezone	String		New User's time zone setting. It has to be either one of the following entries: Please make sure the parameter is properly URL encoded. E.g. GMT-08:00 (PST) => GMT%2d08%3a00+%28PST%29 Please refer to Appendix B for the list of available timezone.
Bandwidth	Number		0 = Unlimited Bandwidth
Notes	String		Notes for the user.
Email	String		New user's contact email
SuspendPaidUserDate	String		A date in yyyy-MM-dd format
Replicated	Boolean		Whether to replicate the new user. { Y N }
Return Value:			
			If successful, returns <OK/> If there is an error, returns <err>%ERROR_MESSAGE%</err>
Example:			
			http://BACKUP_SERVER/obs/api/ModifyUser.do?SysUser=system&SysPwd=system&LoginName=test&Password=abc&Alias=Testing&Language=en&Type=PAID&Status=ENABLE&Quota=100000&UseHome=E%3A%5C&EnableMSSQL=Y&EnableMSExchange=Y&EnableOracle=Y&EnableLotusNotes=Y&EnableLotusDomino=Y&EnableMySQL=Y&EnableInFileDelta=Y&EnableShadowCopy=Y&EnableCDP=Y&EnableShadowProtectBareMetal=Y&EnableWinServer2008BareMetal=Y&EnableDeltaMerge=Y&EnableMsVm=Y&MsVmQuota=10&EnableVMware=Y&VMwareQuota=10&AppendContact=Y&Contact1=john.john&Email1=john.john%40someDomain%2Ecom&Contact2=paul&Email2=paul%40anotherDomain%2Ecom&EnableExchangeMailbox=Y&ExchangeMailboxQuota=10&ClientType=OBM

24.7 Deleting User

The following table describes all information required to invoke the [Remove User] API to remove an existing user from an AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/RemoveUser.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	Login name of the user	
Return Value:			
If successful, returns <OK/>			
If there is an error, returns <err>%ERROR_MESSAGE%</err>			
i. LoginName incorrect or does not exist			
<err>[UserCacheManager.NoSuchUserExpt] User '%USER_NAME%' not found.</err>			
ii. Blank Login name specified			
<err>[Error] Parameter LoginName is null/empty!</err>			
Example:			
http://BACKUP_SERVER/obs/api/RemoveUser.do?SysUser=system&SysPwd=system&LoginName=test			

24.8 Listing Users

The following table describes all information required to invoke the [List Users] API to get a list of all users available within AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/ListUsers.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginNameOnly	String	Whether to display login names only	
ClientTypeOnly	String	Whether to display client types and login names only.	
Owner	String	<p>Owner of backup users</p> <p>If parameter "Owner" is not used, all backup user accounts will be listed.</p> <p>If parameter "Owner" is used but empty, all backup users created by admin role system users will be listed.</p> <p>If parameter "Owner" is used and valid, all backup users created by the specified system user (admin or sub admin) will be listed.</p>	
Host	String	(Optional) Use with AhsayRDR Only) AhsayOBS's URL	
Return Value:			
<p>If successful, returns</p> <pre><users> <User LoginName="test1" Alias="" UserType="PAID" ClientType="OBM" Quota="10737418240" Timezone="GMT+08:00 (CST)" Language="en" DataFile="1" DataSize="1536" RetainFile="0" RetainSize="0" EnableMSSQL="Y" EnableMSExchange="Y" EnableOracle="Y" EnableLotusNotes="Y" EnableLotusDomino="Y" EnableMySQL="Y" EnableInFileDelta="Y" EnableShadowCopy="Y" EnableExchangeMailbox="N" ExchangeMailboxQuota="0" EnableNASClient="Y" EnableDeltaMerge="Y" EnableMsVm="N" MsVmQuota="0" EnableVMware="N" VMwareQuota="0" Bandwidth="0" Notes="" Status="ENABLE" RegistrationDate="1302687743242" SuspendPaidUser="N" SuspendPaidUserDate="20140503" LastBackupDate="1302699594652" Owner="" EnableCDP="Y" EnableShadowProtectBareMetal="Y" EnableWinServer2008BareMetal="Y"><Contact</pre>			

	<pre>Name=""Email="www@qqq.com"/> </user> ... </users></pre> <p>If there is an error, returns <err>%ERROR_MESSAGE%</err></p>
	<p>Where</p> <p>LoginName = login name</p> <p>Alias = user's alias</p> <p>UserType = user type { PAID TRIAL }</p> <p>ClientType = client type { OBM ACB }</p> <p>Quota = quota in bytes</p> <p>Timezone = user's time zone</p> <p>Language = user's language</p> <p>DataFile = total number of files in the data area</p> <p>DataSize = total amount of bytes in the data area</p> <p>RetainFile = total number of files in the retention area</p> <p>RetainSize = total amount of bytes in the retention area</p> <p>EnableMSSQL = MS SQL enabled { Y N }</p> <p>EnableMSExchange = MS Exchange enabled { Y N }</p> <p>EnableOracle = Oracle enabled { Y N }</p> <p>EnableLotusNotes = Lotus Notes enabled { Y N }</p> <p>EnableLotusDomino = Lotus Domino enabled { Y N }</p> <p>EnableMySQL = MySQL enabled { Y N }</p> <p>EnableInFileDelta = In-file Delta enabled { Y N }</p> <p>EnableShadowCopy = Shadow Copy enabled { Y N }</p> <p>EnableExchangeMailbox = MS Exchange Mailbox enabled { Y N }</p> <p>EnableNASClient = AhsayOBM JVM Royalty enabled { Y N }</p> <p>EnableDeltaMerge = Delta Merge enabled { Y N }</p> <p>ExchangeMailboxQuota = MS Exchange Mailbox quota</p> <p>EnableMsVm= HyperV module enable { Y N }</p> <p>MsVmQuota= HyperV Guest VM quota</p> <p>EnableVMware= VMware module enable { Y N }</p> <p>VMwareQuota= VMware Guest VM quota</p> <p>Bandwidth = user's bandwidth</p> <p>Notes = user's notes</p> <p>Status = status of user account { ENABLE SUSPENDED }</p> <p>RegistrationDate = registration date of user account</p> <p>SuspendPaidUser = Status of the Paid User { Y N }</p> <p>SuspendPaidUserDate = Date t o suspend Paid User [yyyy-MM-dd]</p> <p>LastBackupDate = Date of last backup [Unix time format in millisecond]</p> <p>Owner = user's owner</p> <p>EnabledCDP = Continuous Data Protection (CDP) enabled { Y N }</p> <p>EnableShadowProtectBareMetal = ShadowProtectBareMetal enabled { Y N }</p> <p>EnableWinServer2008BareMetal = WinServer2008BareMetal enabled { Y N }</p>
Example:	
	<p>http://BACKUP_SERVER/obs/api/ListUsers.do?SysUser=system&SysPwd=system</p>
	<p>http://BACKUP_SERVER/obs/api/ListUsers.do?SysUser=system&SysPwd=s</p>

ystem&Host=obs.yourserver.com
http://BACKUP_SERVER/obs/api/ListUsers.do?SysUser=system&SysPwd=system&Owner=testing

24.9 Getting User Information

The following table describes all information required to invoke the [Get User] API to get a user's account information.

URL:		
http://BACKUP_SERVER/obs/api/GetUser.do		
Available since version:		
Pre-v6.0		
Parameters:		
Key	Value	Descriptions
SysUser	String	AhsayOBS's System Username
SysPwd	String	AhsayOBS's System Password
LoginName	String	The user's login name
Return Value:		
If successful, returns		
<pre><User LoginName="test1" Alias="" UserType="PAID" ClientType="OBM" Status="ENABLE" Quota="10737418240" Timezone="GMT+08:00 (CST)" Language="en" DataFile="1" DataSize="1536" RetainFile="0" RetainSize="0" UncompressedSize="0" UncompressedRetainSize="0" EnableMSSQL="Y" EnableMSExchange="Y" EnableOracle="Y" EnableLotusNotes="Y" EnableLotusDomino="Y" EnableMySQL="Y" EnableInFileDelta="Y" EnableShadowCopy="Y" EnableExchangeMailbox="N" ExchangeMailboxQuota="0" EnableNASClient="Y" EnableDeltaMerge="Y" EnableMsVm="N" MsVmQuota="0" EnableVMware="N" VMwareQuota="0" Bandwidth="0" Notes="" UserHome="E:\AhsayOBS and AhsayRPS\user\test1" RegistrationDate="1302687743242" MailboxUsage="0" SuspendPaidUser="N" SuspendPaidUserDate="20140503" LastBackupDate="1302699594652" Owner="" EnableCDP="Y" EnableShadowProtectBareMetal="Y" EnableWinServer2008BareMetal="Y"><Contact Name="" Email="www@qqq.com"/></User></pre>		
If there is an error, it returns <err>%ERROR_MESSAGE%</err>		
Where		
LoginName = login name		
Alias = user's alias		
UserType = user type { PAID TRIAL }		
ClientType = client type { OBM ACB }		
Status = status of user account { ENABLE SUSPENDED }		
Quota = quota in bytes		
Timezone = user's timezone		
Language = user's language		

<p>DataFile = total number of files in the data area DataSize = total amount of bytes in the data area RetainFile = total number of files in the retention area RetainSize = total amount of bytes in the retention area UncompressedSize = total amount (bytes) of uncompressed file size in data area EnableMSSQL = MS SQL enabled { Y N } EnableMSExchange = MS Exchange enabled { Y N } EnableOracle = Oracle enabled { Y N } EnableLotusNotes = Lotus Notes enabled { Y N } EnableLotusDomino = Lotus Domino enabled { Y N } EnableMySQL = MySQL enabled { Y N } EnableInFileDelta = In-file Delta enabled { Y N } EnableShadowCopy = Shadow Copy enabled { Y N } EnableExchangeMailbox = MS Exchange Mailbox enabled { Y N } ExchangeMailboxQuota = MS Exchange Mailbox quota EnableNASClient = AhsayOBM JVM Royalty enabled { Y N } EnableDeltaMerge = Delta Merge enabled { Y N } EnableMsVm= HyperV module enable { Y N } MsVmQuota= HyperV Guest VM quota EnableVMware= VMware module enable { Y N } VMwareQuota= VMware Guest VM quota Bandwidth = user's bandwidth Notes = user's notes UserHome = the directory where AhsayOBS stores the backup files and backup logs RegistrationDate = registration date of user account MailboxUsage = the number of mailboxes used SuspendPaidUser = Status of the Paid User { Y N } SuspendPaidUserDate = Date to suspend Paid User [yyyy-MM-dd] LastBackupDate = Date of last backup [Unix time format in millisecond] Owner = user's owner EnabledCDP = Continuous Data Protection (CDP) enabled { Y N } EnableShadowProtectBareMetal = ShadowProtectBareMetal enabled { Y N } EnableWinServer2008BareMetal = WinServer2008BareMetal enabled { Y N }</p>
<p>Example:</p>
<p>http://BACKUP_SERVER/obs/api/GetUser.do?SysUser=system&SysPwd=system&LoginName=John</p>

24.10 Adding a Backup Set

The following table describes all information required to invoke the [Add Backup Set] API to add a new backup set.

URL:			
http://BACKUP_SERVER/obs/api/AddBackupSet.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	The user's login name	
Return Value:			
<p>If successful, returns</p> <pre><BackupSet ID="1122260638375"> </BackupSet ></pre> <p>If there is an error, returns <code><err>%ERROR_MESSAGE%</err></code></p> <p>i. Login name incorrect or does not exist</p> <pre><err>[UserCacheManager.NoSuchUserExpt] User '%USER_NAME%' not found.</err></pre> <p>ii. Blank Login name specified</p> <pre><err>[Error] Parameter LoginName is null/empty!</err></pre> <p>iii. Cannot perform an add backup set to AhsayACB user account</p> <pre><err>[Error] ACB backup user can only have one backup set.</err></pre>			
<p>where ID = new backup set ID</p>			
Example:			
http://BACKUP_SERVER/obs/api/AddBackupSet.do?SysUser=system&SysPwd=system&LoginName=John			

24.11 Deleting a Backup Set

The following table describes all information required to invoke the [Delete Backup Set] API to delete a backup set for a particular user.

URL:			
http://BACKUP_SERVER/obs/api/DeleteBackupSet.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	The user's login name	
BackupSetID	String	The ID of the backup set to delete	
Return Value:			
If successful, returns <OK/>			
If there is an error, returns <err>%ERROR_MESSAGE%</err>			
i. Login name incorrect or does not exist			
<err>[UserCacheManager.NoSuchUserExpt] User '%USER_NAME%' not found.</err>			
ii. Blank Login name specified			
<err>[Error] Parameter LoginName is null/empty!</err>			
iii. Blank BackupSetID specified			
<err>[Error] Parameter BackupSetID is null/empty!</err>			
Example:			
http://BACKUP_SERVER/obs/api/DeleteBackupSet.do?SysUser=system&SysPwd=system&LoginName=John&BackupSetID=1122260638375			

24.12 Listing Backup Sets

The following table describes all information required to invoke the [List Backup Sets] API to list all the backup sets for a particular user.

URL:			
http://BACKUP_SERVER/obs/api/ListBackupSets.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	The user's login name	
Return Value:			
If successful, returns			
<pre><BackupSets> <BackupSet ID="1302673387980" Name="BackupSet" Type="FILE" /><BackupSet ID="1302673465574" Name="BackupSet (2)" Type="VMware Virtualization" /><BackupSet ID="1303955350843" Name="BackupSet (3)" Type="Microsoft Windows Virtualization" /><BackupSet ID="-11302687382211" Name="enforced_test_win" Type="FILE" /><BackupSet ID="1302682595966" Name="ESXi-demo" Type="VMware Virtualization" /><BackupSet ID="1302684999063" Name="hyperv" Type="Microsoft Windows Virtualization" /><BackupSet ID="1303205174271" Name="HyperV-VSS" Type="Microsoft Windows Virtualization" /><BackupSet ID="1303203620407" Name="Volumes" Type="FILE" /> </BackupSets></pre>			
If there is an error, returns <code><err>%ERROR_MESSAGE%</err></code>			
i. LoginName incorrect or does not exist			
<code><err>[UserCacheManager.NoSuchUserExpt] User '%USER_NAME%' not found.</err></code>			
ii. Blank Login name specified			
<code><err>[Error] Parameter LoginName is null/empty!</err></code>			
Example:			
http://BACKUP_SERVER/obs/api/ListBackupSets.do?SysUser=system&SysPwd=system&LoginName=John			

24.13 Get Backup Set

The following table describes all information required to invoke the [Get Backup Set] API to get a backup set.

URL:			
http://BACKUP_SERVER/obs/api/GetBackupSet.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	The user's login name	
BackupSetID	String	The backup set ID	
ShowStatusOnly	String	<p>If ShowStatusOnly="N" (default if no value is specified) the full backup set configuration will be returned.</p> <p>If ShowStatusOnly="Y" a summary of the backup set configuration will be returned</p>	
Return Value:			
<p>If successful, returns</p> <p>When ShowStatusOnly="N"</p> <pre><BackupSet ID="1303106066451" Name="Exchange 2010 DB" Type="Microsoft Exchange Server"><RunBackup Run="N" BackupType=""/></BackupSet></pre> <p><u>When ShowStatusOnly="N" or if ShowStatusOnly is omitted from the API</u></p> <pre><BackupSet ID="1303106066451" Name="Exchange 2010 DB" TransferBlockSize="262144" FollowSymbolicLink="N" WindowsFollowLink="Y" Os="" Type="Microsoft Exchange Server" AdminUsername="" AdminPassword="" WorkingDir="E:\temp" OracleSID="" Port="" Host="" LogRetentionDays="60" NotesINI="" BackupSystemState="N" LanDomain="CSMAIL2010" LanUsername="Administrator" LanPassword="" LastBackupRun="1305550934179" LastBackupAccess="1305550944476" EnableInFileDelta="Y" MinDeltaFileSize="26214400" DeltaBlockSize="-1" MaxNumOfDelta="100" MaxDeltaRatio="50" EnableShadowCopy="N" EnableOfflineBackup="N" EnableLogoutBackup="N" FullBackup="N" LastBackupCompleted="1305550946617" BackupIntervalDay="1" BackupIntervalHour="0" LogoutType="" OfflineNotificationDay="7" DeleteTempFile="N" SqlServer="" DefaultDeltaType="I" TotalUncompressedDataSize="6471213979" NumberOfFiles="165" TotalBackupSetSize="3124437892" TotalBSetRetainUncompress="390795288" TotalBSetRetainFileNo="358" TotalBsetRetainFileSize="19905055" TotalBsetRestoreSize="0"</pre>			

<pre>TotalBsetRestoreNo="0" ScheduleHost="WIN2008A" UploadPermission="N" EnableDeltaMerge="N" Version="14" OfflineBackupComputerName="" LogoutBackupReminderComputerName="" > <SelectedSource>Microsoft Exchange Server\Microsoft Information Store</SelectedSource><RunBackup Run="N" BackupType=""/> <WeeklySchedule ID="1302495192421" Name="Database Backup Schedule" Sun="N" Mon="N" Tue="N" Wed="N" Thu="Y" Fri="N" Sat="N" Hour="21" Minute="0" Duration="-1" BackupType="DATABASE" LastUpdated="0" Interval="-1" EnableSkipBackup="N"/> <WeeklySchedule ID="1305623577798" Name="Transaction log Backup Schedule" Sun="Y" Mon="Y" Tue="Y" Wed="Y" Thu="N" Fri="N" Sat="N" Hour="21" Minute="0" Duration="-1" BackupType="LOG" LastUpdated="1305550944476" Interval="-1" EnableSkipBackup="N"/> <RetentionPolicy Unit="DAYS" Period="7"> <RetentionSetting ID="1305623577798" Name="Default" OverlapSensitive="N"> </RetentionSetting> </RetentionPolicy> <ExtraLocal Backup ENABLED="N" Zip="Y" BackupTo="C:\LocalBackup" SkipOffsiteBackup="N" SetLocalCopyPermission="N"/> <DeltaWeeklySchedule Sun="" Mon="" Tue="" Wed="" Thu="" Fri="" Sat=""/> <DeltaMonthlySchedule Date="" Occurrence="" Criteria="" JAN="" FEB="" MAR="" APR="" MAY="" JUN="" JUL="" AUG="" SEP="" OCT="" NOV="" DEC=""/> <Cdp EnableCDP="N" CdpTimeMarkInterval="60" CdpMinUpdateInterval="10" Type="all- volume" ExcludeSystemFiles="N" CdpComputerName="" IdlebkgpIsConsiderCpu="N" IdlebkgpCpuTsh="0" IdlebkgpIsConsiderNwk="N" IdlebkgpNwkTsh="131072" IdlebkgpIsConsiderIpt="N" IdlebkgpIptObserveForSecond="60"> </Cdp> <EncryptingKey KeyType="PWD" Algorithm="AES" Mode="ECB" Length="256" Key="6ZoYxCjLONXyYIU2eJIuAw=="/> </BackupSet></pre> <p>If there is an error, returns</p> <pre><err>[UserCacheManager] User 'Johnny' not found.</err> <err>Backup Set for ID='1065821983563' not found</err></pre>	<p>where under</p> <pre>Tag <BACKUP_SET> ID = backup set ID Name = backup set name TransferBlockSize = block size for transfer FollowSymbolicLink = follow symbolic link (Linux only) Os = Operating System Type = backup set type AdminUsername = administrator user name AdminPassword = administrator password WorkingDir = temporary working directory OracleSID = Oracle SID setting Port = Oracle port number Host = Oracle hostname</pre>
---	--

LogRetentionDays = retention day logging
 NotesINI = path location of notes.ini file
 BackupSystemState = whether to backup system state
 LanDomain = LAN domain name
 LanUsername = LAN user name
 LanPassword = LAN password
 LastBackupRun = time of last backup run
 LastBackupAccess = time of last backup
 EnableInFileDelta = enabling in-file delta feature
 MinDeltaFileSize = minimum delta file size setting field
 DeltaBlockSize = delta block size setting field
 MaxNumOfDelta = maximum delta number setting field
 MaxDeltaRatio = maximum delta ratio setting field
 EnableShadowCopy = enabling shadow copy feature field
 EnableOfflineBackup = enabling offline copy feature field
 EnableLogoutBackup = enabling logout backup feature field
 FullBackup = enabling full backup field
 LastBackupCompleted = time when the last backup was completed
 BackupIntervalDay = Offline backup day interval
 BackupIntervalHour = Offline backup hour interval
 LogoutType = unused
 OfflineNotificiationDay = Offline backup email reminder days
 DeleteTempFile = Remove temporary files after backup
 SqlServer = SQL server hostname
 DefaultDeltaType = Default in-file delta type
 TotalUncompressedDataSize = Total uncompressed size in bytes of the data area
 NumberOfFiles = Total number of files in the data area
 TotalBackupSetSize = Total compressed size in bytes of the data area
 TotalBSetRetainUncompress = Total uncompressed size in bytes of the retention area
 TotalBSetRetainFileNo = Total number of files in the retention area
 TotalBsetRetainFileSize = Total compressed size in bytes of the retention area
 TotalBsetRestoreFileSize = Total size in bytes of the files restored
 TotalBsetRestoreNo = Total number of restoration done
 ScheduleHost = Computer name of this backup set that the scheduler will use to determine whether to run
 EnableDeltaMerge = Delta merge enabled { Y | N }
 Version = Version number for MS Exchange Server

Tag < SelectedSource >
 SelectedSource = selected sources for backup

Tag < DeseletedSource >
 DeseletedSource = deselected sources for backup

Tag <Status>
 Run = Whether the backup is pending
 BackupType = Backup type { DATABASE | LOG | DIFFERENTIAL | LOG | COMPLETE | INCREMENTAL }

Tag < DailySchedule >
 ID = schedule ID
 Name = schedule name
 Hour = time setting for such schedule
 Minute = time setting for such schedule
 Duration = how long to run. Use -1 for "Stop on completion"
 BackupType = Backup set type
 Tag < WeeklySchedule >
 ID = schedule ID
 Name = schedule name
 Sun = enable field
 Mon = enable field
 Tue = enable field
 Wed =enable field
 Thu = enable field
 Fri = enable field
 Sat = enable field
 Hour = time setting for such schedule
 Minute = time setting for such schedule
 Duration = how long to run. Use -1 for "Stop on completion"
 BackupType = Backup set type

 Tag < MonthSchedule >
 ID = schedule ID
 Name = schedule name
 Date = exact day of the month. When "0" use occurrence and criteria.
 Occurrence= occurrence to run e.g. First, Second, Third, Forth Last
 Criteria = day to run e.g. Monday, Tuesday, Wednesday, Thursday, Friday, Saturday, Sunday
 Hour = time setting for such schedule
 Minute = time setting for such schedule
 Duration = how long to run. Use -1 for "Stop on completion"
 BackupType = Backup set type
 Tag < CustomSchedule >
 ID = schedule ID
 Name = schedule name
 BackupType = Backup set type
 Date = the date to run this schedule
 Hour = time setting for such schedule
 Minute = time setting for such schedule
 Duration = how long to run. Use -1 for "Stop on completion"

 Tag < Filter>
 ID = filter ID
 Name = filter name
 Type = filter type
 TopDir = the top most directory to apply this filter
 Include = filter mode
 Only = filter mode
 ApplyToDir = applying to such directory

ApplyToFile = applying to such file

Tag < Pattern>

Pattern = the filter pattern to apply

Tag < RetentionPolicy >

Unit= type for the retention policy, by JOB, DAYS, or CUSTOMIZE

Period= days for the policy

Tag < RetentionSetting >

ID = retention ID

OverlapSensitive = enable feature setting

Tag < Setting>

ID = retention ID

Name = retention name

Type = retention type. Allowed values are { DAILY | WEEKLY | MONTHLY | QUARTERLY | YEARLY | CUSTOM }

NumOfCopiesToKeep = number of copies to keep

DateType = normally empty. Use "EXACT" when the date is known.

Sun, Mon, Tue, Wed, Thu, Fri, Sat = days enabled

Day, Week, Month, Year = date enabled

Tag < PreBackupCommand>

ID = pre-command ID

Name = pre-command name

Path = path for such pre command

WorkingDir = directory for such pre-command

Tag < PostBackupCommand >

ID = post command ID

Name = post command name

Path = path for such post command

WorkingDir = directory for such post command

Tag < AllowedIP >

ID = allowedIP ID

StartIP = Start of online restore IP range

EndIP = End of online restore IP range

Tag < ExtraLocalBackup >

ENABLED = enable "Extra Local Copy" feature field

Zip = zip the copied file feature

BackupTo = location to save extra copy

SkipOffsiteBackup = whether to skip off-site backup

SetLocalCopyPermission = set local copy permission

Tag < DeltaWeeklySchedule>

Sun, Mon, Tue, Wed, Thu, Fri, Sat = advance delta weekly schedule enabled. { I | D | F }

Tag < DeltaMonthlySchedule>

Date = exact day of the month. When "0" use occurrence and criteria.
 Occurrence= occurrence to run e.g. First, Second, Third, Forth Last
 Criteria = day to run e.g. Monday, Tuesday, Wednesday, Thursday, Friday, Saturday, Sunday
 Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, Dec = advance monthly schedule enabled. { I | D | F }

Tag <Cdp>

EnableCdp = Continuous Data Protection (CDP) Enabled { Y | N }

CdpTimeMarkInterval = the interval of point-in-time views generated by CDP

CdpMinUpdateInterval = the minimum interval that repeatedly updated files are backup again

Type = Continuous Data Protection (CDP) type { all-volume | backup-source | custom-source }

ExcludeSystemFiles = exclude system files { Y | N }

CdpComputerName = Computer name of this backup set that the Cdp will use to determine whether to run

IdlebkgpIsConsiderCpu = whether to consider Cpu { Y | N }

IdlebkgpCpuTsh = the thredhold value of Cpu. If Cpu usage keeps below than the threshold for 1 minute, then Cpu is idle.

IdlebkgpIsConsiderNwk = whether to consider network (only the network activity sending out) { Y | N }

IdlebkgpNwkTsh = the thredhold value of network, in unit of "bytes sent per second". If network usage is below than the thredhold 2 second, then network is idle

IdlebkgpIsConsiderIpt = whether to consider input activity { Y | N }

IdlebkgpIptObserveForSecond = how long it observe. If no keyboard stroke and mouse movement within the observer period, then input activity is idle.

Tag <CdpFilter>

ID = Continuous Data Protection (CDP) filer ID

Name = Continuous Data Protection (CDP) filter name

Type = Continuous Data Protection (CDP) filter type

TopDir = the top most directory to apply this filter

Include = filter mode

ApplyToDir = applying to such directory

ApplyToFile = applying to such file

Tag <Pattern>

Pattern = the filter pattern to apply

Tag <EncryptingKey>

KeyType = encrypting key type { PWD | CUSTOM | NOENCRYPT }

Algorithm = encryptinh key algorithm { TwoFish | DESede | AES }

Mode = encrypting key mode { ECB | CBC }

Length = encrypting key length

Key = hashed encrypting key

Example:

http://BACKUP_SERVER/obs/api/GetBackupSet.do?SysUser=system&SysP

wd=system&LoginName=John&BackupSetID=1077097041763&ShowStatusOnly=N

24.14 Updating a Backup Set

The following table describes all information required to invoke the [Update Backup Set] API to update a backup set. Note, use [Get Backup Set] API above to retrieve a backup set and save it as an xml file; modify the file as you need, and post it as a content using parameter name "Profile" when calling [Update Backup Set] API.

URL:			
http://BACKUP_SERVER/obs/api/UpdateBackupSet.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	The user's login name	
Profile	String	The whole content of backup set in XML format posted up when calling this API	
Return Value:			
If successful, returns <OK/>			
If there is an error, returns <err>%ERROR_MESSAGE%</err>			
Example:			
http://BACKUP_SERVER/obs/api/UpdateBackupSet.do?SysUser=system&SysPwd=system&LoginName=John			

24.15 Listing Backup Jobs

The following table describes all information required to invoke the [List Backup Jobs] API to get a list of all backup jobs for all backup sets.

URL:		
http://BACKUP_SERVER/obs/api/ListBackupJobs.do		
Available since version:		
Pre-v6.0		
Parameters:		
Key	Value	Descriptions
SysUser	String	AhsayOBS's System Username
SysPwd	String	AhsayOBS's System Password
LoginName	String	The user's login name
CDP	Boolean	Continuous Data Protection { Y N }
SkipEmpty	String	Skip if backup job has no files { Y N }
Return Value:		
<p>If successful, returns</p> <pre><BackupSets> <BackupSet ID="1121746638656"> <BackupJob ID="2005-12-29-12-00-00" /> <BackupJob ID="2005-12-30-12-00-00" /> <BackupJob ID="2005-12-31-12-00-00" /> </BackupSet> ... </BackupSets></pre> <p>If there is an error, returns <code><err>%ERROR_MESSAGE%</err></code></p> <p>i. LoginName incorrect or does not exist</p> <pre><err>[UserCacheManager.NoSuchUserExpt] User '%USER_NAME%' not found.</err></pre> <p>ii. Blank Login name specified</p> <pre><err>[Error] Parameter LoginName is null/empty!</err></pre>		
<p>Where under</p> <p>Tag <code><BackupSet></code> ID = backup set ID</p> <p>Tag <code><BackupJob></code> ID = backup job ID</p>		
Example:		
http://BACKUP_SERVER/obs/api/ListBackupJobs.do?SysUser=system&SysPwd=system&LoginName=John		
http://BACKUP_SERVER/obs/api/ListBackupJobs.do?SysUser=sys		

tem&SysPwd=system&LoginName=John&CDP=Y

http://BACKUP_SERVER/obs/api/ListBackupJobs.do?SysUser=system&SysPwd=system&LoginName=John&CDP=Y&SkipEmpty=Y

24.16 Listing Backup Job Status

The following table describes all information required to invoke the [List Backup Job Status] API to get a list of all backup jobs for all backup sets.

URL:		
http://BACKUP_SERVER/obs/api/ListBackupJobStatus.do		
Available since version:		
Pre-v6.0		
Parameters:		
Key	Value	Descriptions
SysUser	String	AhsayOBS's System Username
SysPwd	String	AhsayOBS's System Password
LoginName	String	The user's login name
BackupDate	String	A date in yyyy-MM-dd format
Cdp	Boolean	Continuous Data Protection { Y N }
Return Value:		
<p>If successful, returns</p> <pre><BackupJobs BackupDate="2007-01-02" > <BackupJob ID="2007-01-02-02-01-01" LoginName="demo" StartTime="2007-01-02 02:01:01" EndTime="2007-01-02 02:01:04" BackupJobStatus="BS_STOP_SUCCESS" BackupSetID="1190692945178" /> <BackupJob ID="2007-01-02-16-45-45" LoginName="demo" StartTime="2007-01-02 16:45:45" EndTime="2007-01-02 16:45:48" BackupJobStatus="BS_STOP_SUCCESS" BackupSetID="1190692945178" /> </BackupJobs></pre> <p>If there is a Backup Job in progress, it returns "Backup in progress".</p> <p>If there is an error, it returns <code><err>%ERROR_MESSAGE%</err></code></p> <p>i. LoginName incorrect or does not exist</p> <pre><err>[UserCacheManager.NoSuchUserExpt] User '%USER_NAME%' not found.</err></pre> <p>ii. Blank Login name specified</p> <pre><err>[Error] Parameter LoginName is null/empty!</err></pre> <p>iii. Either incorrect backup job date specified or No backup job was run for the specified date</p> <pre><err>[Error] No Backup Job on that day</err></pre>		

	<p>iv. Incorrect Backupdate format specified. BackupDate=YYYY-MM-DD</p> <p><code><err>[Error] Parameter BackupDate is not in correct format!</err></code></p>
	<p>where under</p> <p>Tag <BackupJobs></p> <p>BackupDate = date of backup</p> <p>Tag <BackupJob></p> <p>ID = backup job ID</p> <p>LoginName = user name</p> <p>StartTime = job start time</p> <p>EndTime = job end time</p> <p>BackupJobStatus = the status of the backup job as follows:</p> <ol style="list-style-type: none"> 1. BS_STOP_SUCCESS = backup completed successfully 2. BS_STOP_BY_SYSTEM_ERROR = backup stopped due to system error 3. BS_STOP_BY_SCHEDULER = backup stopped by scheduler 4. BS_STOP_BY_USER = backup stopped by user 5. BS_STOP_BY_QUOTA_EXCEEDED = backup stopped due to quota exceeded 6. BS_STOP_SUCCESS_WITH_ERROR = backup completed with errors 7. BS_STOP_SUCCESS_WITH_WARNING = backup completed with warnings 8. BS_STOP_MISSED_BACKUP = backup missed 9. Empty = backup in progress 10. Others = other client errors not defined above. <p>BackupSetID = backup set ID</p>
Example:	
	<p>http://BACKUP_SERVER/obs/api/ListBackupJobStatus.do?SysUser=system&SysPwd=system&LoginName=John&BackupDate=2007-01-08</p>

24.17 Getting Backup Job Report

The following table describes all information required to invoke the [Get Backup Job Report] API to get a backup job status.

URL:			
http://BACKUP_SERVER/obs/api/GetBackupJobReport.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	The user's login name	
BackupSetID	String	A backup set ID	
BackupJobID	String	A backup job ID	
Cdp	String	Continuous Data Protection { Y N }	
Return Value:			
If successful, returns			
<pre><BackupJob ID="2005-07-19-12-11-20" StartTime=" 2005-07-19 12:11:20" EndTime="2005-07-19 12:21:20" BackupJobStatus="BS_STOP_SUCCESS" NumOfErrorEntries="0" NumOfWarnEntries="0" NumOfNewFiles="1" TotalNewFilesSize="132864" TotalUnzipNewFilesSize="3951322" NewFilesZipRatio="96%" NumOfUpdatedFiles="1" TotalUpdatedFilesSize="132864" TotalUnzipUpdatedFilesSize="3951322" UpdatedFilesZipRatio="96%" NumOfUpdatedPermissionFiles="1" TotalUpdatedPermissionFileSize="132864" TotalUnzipUpdatedPermissionFiles NumOfDeletedFiles="1" TotalDeletedFilesSize="132864" TotalUnzipDeletedFilesSize="3951322" DeletedFilesZipRatio="96%" NumOfMovedFiles="1" TotalMovedFilesSize="132864" TotalUnzipMovedFilesSize="3951322" MovedFilesZipRatio="96%"> <Info Timestamp="2005-12-31 12:59:59" Message="???????" /> ... <Warn Timestamp="2005-12-31 12:59:59" Message="???????" /> ... <Error Timestamp="2005-12-31 12:59:59" Message="???????" /> ... <NewFile LastModified="2005-12-31 12:59:59" Name="C:\abc.doc" FileSize="374" UnzipFilesSize="11656" Ratio="63%"/> ... <UpdatedFile LastModified="2005-12-31 12:59:59" Name="C:\abc.doc" FileSize="374" UnzipFilesSize="11656" Ratio="63%"/> <UpdatedPermissionFile LastModified="2005-12-31 12:59:59" Name="C:\abc.doc" FileSize="374" UnzipFilesSize="11656" Ratio="63%"/></pre>			

```

...
<DeletedFile LastModified="2005-12-31 12:59:59" Name="C:\abc.doc"
FileSize="374" UnzipFileSize="11656" Ratio="63%"/>
...
<MovedFile LastModified="2005-12-31 12:59:59" FromFile="C:\abc.doc"
ToFile="C:\abc.doc"
      FileSize="374" UnzipFileSize="11656" Ratio="63%"/>
...
</BackupJob>

```

If there is an error, returns <err>%ERROR_MESSAGE%</err>

where under
Tag <BackupJob>
ID = backup job ID
StartTime = backup job start time
EndTime = backup job end time
BackupJobStatus = status of backup job
NumOfErrorEntries = number of backup job errors
NumOfWarnEntries = number of backup job warnings
NumOfNewFiles = number of new files
TotalNewFilesSize = new files size
TotalUnzipNewFilesSize = new files size before zip
NewFilesZipRatio = ratio of new files being zipped
NumOfUpdatedFiles = number of updated files
TotalUpdatedFilesSize = updated files size
TotalUnzipUpdatedFilesSize = updated files size before zip
UpdatedFilesZipRatio = ratio of updated files being zipped
NumOfUpdatedPermissionFiles = number of updated permission files
TotalUpdatedPermissionFilesSize = updated permission files size
TotalUnzipUpdatedPermissionFilesSize = updated permission files size before zip
UpdatedPermissionFilesZipRatio = ratio of updated permission files being zipped
NumOfDeletedFiles = number of deleted files
TotalDeletedFilesSize = deleted files size
TotalUnzipDeletedFilesSize = deleted files size before zip
DeletedFilesZipRatio = ratio of deleted files being zipped
NumOfMovedFiles = number of moved files
TotalMovedFilesSize = move files size
TotalUnzipMovedFilesSize = moved files size before zip
MovedFilesZipRatio = ratio of moved files being zipped
Tag <Info>, <Warn>, <Error>
TimeStamp = time of this message
Message = message text
Tag <NewFile>, <UpdatedFile>, <UpdatedPermissionFile>, <DeletedFile>, <MovedFile>
Name = filename
FileSize = filesize
LastModified = last modified time of such file
UnzipFileSize = original file size before zipping

Ratio = ratio of the size being zipped
Example:
http://BACKUP_SERVER/obs/api/GetBackupJobReport.do?SysUser=system&SysPwd=system&LoginName=john&BackupSetID=1108378758790&BackupJobID=2007-01-08-16-02-07

24.18 Getting Backup Job Report Summary

The following table describes all information required to invoke the [Get Backup Job Report Summary] API to get a backup job status.

URL:			
http://BACKUP_SERVER/obs/api/GetBackupJobReportSummary.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	The user's login name	
BackupSetID	String	A backup set ID	
BackupJobID	String	A backup job ID	
Cdp	Boolean	Continuous Data Protection { Y N }	
Return Value:			
If successful, returns			
<pre><BackupJob ID="2007-01-08-16-02-07" StartTime="2007-01-08 16:02:07" EndTime="2007-01-08 16:02:12" BackupJobStatus="BS_STOP_SUCCESS" NumOfWarnEntries="0" NumOfErrorEntries="0" NumOfNewFiles="15" TotalNewFilesSize="790256" NumOfUpdatedFiles="0" TotalUpdatedFilesSize="0" NumOfDeletedFiles="0" TotalDeletedFilesSize="0" NumOfMovedFiles="0" TotalMovedFilesSize="0" NumOfUpdatedPermissionFiles="0" TotalUpdatedPermissionFilesSize="0" NumOfCopiedFiles="0" TotalCopiedFilesSize="0"> </BackupJob></pre>			
If there is an error, returns <err>%ERROR_MESSAGE%</err>			
where under Tag <BackupJob> ID = backup job ID StartTime = backup job start time EndTime = backup job end time JobStatus = status of backup job NumOfErrorEntries = number of backup job errors			

<p>NumOfWarnEntries = number of backup job warnings NumOfNewFiles = number of new files TotalNewFilesSize = new files size NumOfUpdatedFiles = number of updated files TotalUpdatedFilesSize = updated files size NumOfDeletedFiles = number of deleted files TotalDeletedFilesSize = deleted files size NumOfMovedFiles = number of moved files TotalMovedFilesSize = move files size NumOfUpdatedPermissionFiles = number of updated file permission files TotalUpdatedPermissionFilesSize = updated file permission files size NumOfCopiedFiles = number of copied files TotalCopiedFilesSize = copied files size</p>
<p>Example:</p>
<p>http://BACKUP_SERVER/obs/api/GetBackupJobReportSummary.do?SysUser=system&SysPwd=system&LoginName=john&BackupSetID=1108378758790&BackupJobID=2007-01-08-16-02-07</p>

24.19 Listing Backup Files

The following table describes all information required to invoke the [List Backup Files] API to get all backup files by given a directory.

URL:			
http://BACKUP_SERVER/obs/api/ListBackupFiles.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	The user's login name	
BackupSetID	String	A backup set ID	
BackupJobID	String	A backup job ID	
Path	String	A directory path	
Return Value:			
If successful, returns			
<pre><Files> <File Type="DIR" Name="My Document Folder" /> <File Type="FILE" Name="changeStatus.bat" OriginalFileSize="187" FileSize="1712" BackupByJob="2005-07-25-17-07-07" InBackupJob="Current" LastModified="1109233592750" /> </Files></pre>			
If there is an error, returns <code><err>%ERROR_MESSAGE%</err></code>			
where under Type = File or Directory { FILE DIR } Name = name of the file OriginalFileSize = the original size of the uploaded file FileSize = the actual file size being uploaded BackupByJob = the date when the file was uploaded InBackupJob = The date when the file was last updated LastModified = The time of last modification			
Example:			
http://BACKUP_SERVER/obs/api/ListBackupFiles.do?SysUser=system&SysPwd=system&LoginName=john&BackupSetID=1108378758790&BackupJobID=2007-001-08-16-02-07&Path=C:\Documents%20and%20Settings\john.my.company.			

24.20 Getting User Storage Statistics

The following table describes all information required to invoke the [Getting User Storage Statistics] API to get a list of storage information for a user.

URL:		
http://BACKUP_SERVER/obs/api/GetUserStorageStat.do		
Available since version:		
Pre-v6.0		
Parameters:		
Key	Value	Descriptions
SysUser	String	AhsayOBS's System Username
SysPwd	String	AhsayOBS's System Password
LoginName	String	The user's login name
YearMonth	String	Year and month (yyyy-MM)
Return Value:		
<p>If successful, returns</p> <pre><Statistics YearMonth="2005-07" AvgDataSize="" AvgDataRawSize="" AvgDataNo="" AvgRetainSize="" AvgRetainRawSize="" AvgRetainNo="" AvgUploadSize="" AvgUploadRawSize="" AvgUploadNo="" AvgTotalStorageSize="" AvgTotalStorageRawSize="" AvgTotalStorageNo="" > <Storage Date="2005-07-25" DataSize="0" DataRawSize="0" DataNo="0" RetainSize="0" RetainRawSize="0" RetainNo="0" UploadSize="0" UploadRawSize="0" UploadNo="0" TotalStorageSize="0" TotalStorageRawSize="0" TotalStorageNo="0" /> <Storage Date="2005-07-26" DataSize="0" DataRawSize="0"DataNo="0" RetainSize="0" RetainRawSize="0" RetainNo="0" UploadSize="0" UploadRawSize="0"UploadNo="0" TotalStorageSize="0" TotalStorageRawSize="0"TotalStorageNo="0" /> </Statistics></pre> <p>If there is an error, returns <err>%ERROR_MESSAGE%</err></p>		
<p>where under Tag <Statistics > YearMonth = month of a year AvgDataSize = average size in data area AvgDataRawSize = average size in data area (in bytes) AvgDataNo = average number of files in data area AvgRetainSize = average size in retention area AvgRetainRawSize = average size in retention area (in bytes) AvgRetainNo = average number of files in retention area</p>		

<p> AvgUploadSize = average uploaded size AvgUploadRawSize = average uploaded size (in bytes) AvgUploadNo = average number of uploaded files AvgTotalStorageSize = average size in storage AvgTotalStorageRawSize = average size in storage (in bytes) AvgTotalStorageNo = average number of files in storage Tag <Storage> Date = the date of the statistics calculated DataSize = total data size uploaded DataRawSize = total data size uploaded (in bytes) DataNo = total data number RetainSize = total size in retention area RetainRawSize = total size in retention area (in bytes) RetainNo = total number in retention area UploadSize = total uploaded size UploadRawSize = total uploaded size (in bytes) UploadNo = total uploaded number TotalStorageSize = total size of storage TotalStorageRawSize = total size of storage (in bytes) TotalStorageNo = total storage number </p>
Example:
<p> http://BACKUP_SERVER/obs/api/GetUserStat.do?SysUser=system&SysPwd=system&LoginName=john&YearMonth=2005-07 </p>

24.21 Listing User Storage

[List User Storage] API invokes the [List Users] API with the same parameters to get a list of all users with profile and storage information available within AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/ListUserStorage.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginNameOnly	String	Whether to display login names only	
ClientTypeOnly	String	Whether to display client types and login names only.	
Owner	String	<p>Owner of backup users</p> <p>If parameter "Owner" is not used, all backup users will be listed.</p> <p>If parameter "Owner" is used but empty, all backup users created by admin role system user will be listed.</p> <p>If parameter "Owner" is used and valid, all backup users created by the specified system user (admin or sub admin) will be listed.</p>	
Host	String	(Optional) Use with AhsayRDR Only) AhsayOBS's URL	
Return Value:			
<p>If successful, returns</p> <pre><users> <user LoginName="john" Alias="" UserType="" ClientType="OBM" Quota="" Timezone="GMT+08:00 (CST)" Language="en" DataFile="1234" DataSize="1234" RetainFile="1234" RetainSize="1234" EnableMSSQL="Y" EnableMSExchange="Y" EnableOracle="Y" EnableLotusNotes="Y" EnableLotusDomino="Y" EnableMySQL="Y" EnableInFileDelta="Y" EnableShadowCopy="Y" EnableExchangeMailbox="Y" ExchangeMailboxQuota="10" EnableNASClient="Y" EnableDeltaMerge="Y" Bandwidth="0" Notes="" Status="ENABLE" RegistrationDate=" 1185249951156"</pre>			

<pre>SuspendPaidUser="N" SuspendPaidUserDate="20150930" LastBackupDate="1254821179066" Owner="" EnableCDP="Y" EnableShadowProtectBareMetal="Y" EnableWinServer2008BareMetal="Y"> <Contact name="John (Email1)" email="john@yourcompany.com" /> <Contact name="John (Email2)" email=" johnmy@yourcompany.com " /> </user> </users></pre> <p>If there is an error, returns <err>%ERROR_MESSAGE%</err></p>
<p>Where</p> <ul style="list-style-type: none"> LoginName = login name Alias = user's alias UserType = user type { PAID TRIAL } ClientType = client type { OBM ACB } Quota = quota in bytes Timezone = user's time zone Language = user's language DataFile = total number of files in the data area DataSize = total amount of bytes in the data area RetainFile = total number of files in the retention area RetainSize = total amount of bytes in the retention area EnableMSSQL = MS SQL enabled { Y N } EnableMSExchange = MS Exchange enabled { Y N } EnableOracle = Oracle enabled { Y N } EnableLotusNotes = Lotus Notes enabled { Y N } EnableLotusDomino = Lotus Domino enabled { Y N } EnableMySQL = MySQL enabled { Y N } EnableInFileDelta = In-file Delta enabled { Y N } EnableShadowCopy = Shadow Copy enabled { Y N } EnableExchangeMailbox = MS Exchange Mailbox enabled { Y N } EnableNASClient = AhsayOBM JVM Royalty enabled { Y N } EnableDeltaMerge = Delta Merge enabled { Y N } ExchangeMailboxQuota = MS Exchange Mailbox quota Bandwidth = user's bandwidth Notes = user's notes Status = status of user account { ENABLE SUSPENDED } RegistrationDate = registration date of user account SuspendPaidUser = Status of the Paid User { Y N } SuspendPaidUserDate = Date t o suspend Paid User [yyyy-MM-dd] LastBackupDate = Date of last backup [Unix time format in millisecond] Owner = user's owner EnabledCDP = Continuous Data Protection (CDP) enabled { Y N } EnableShadowProtectBareMetal = ShadowProtectBareMetal enabled { Y N } EnableWinServer2008BareMetal = WinServer2008BareMetal enabled { Y N }
<p>Example:</p>

http://BACKUP_SERVER/obs/api/ListUserStorage.do?SysUser=system&SysPwd=system
http://BACKUP_SERVER/obs/api/ListUserStorage.do?SysUser=system&SysPwd=system&Host=obs.yourserver.com
http://BACKUP_SERVER/obs/api/ListUserStorage.do?SysUser=system&SysPwd=system&Owner=testing

24.22 Get License

The following table describes all information required to invoke the [List License] API to get version of AhsayOBS used and unused licenses available within AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/GetLicense.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
Host	String	(Optional. Use with AhsayRDR only) AhsayOBS's URL	
Return Value:			
<p>If successful, returns</p> <pre><License ProductName="Offsite Backup Suite, OEM Edition" ObsVersion="5.2.4.3" ExpiryDate="Unlimited" SupportExpiryDate="2008/10/31" MaxQuota="Unlimited" LicenseeName="abc" LicenseKey="nFrJk-occ1mvcHkuTrdmcYn" LicenseType="4"><OBM Quota="500" Available="498" Used="2"/><ACB Quota="500" Available="500" Used="0" AcbUsedObmUsers="0"/><MSExchange Quota="500" Available="499" Used="1"/><MSExchangeMail Quota="500" Available="500" Used="0"/><MSSQL Quota="300" Available="299" Used="1"/><Oracle Quota="500" Available="499" Used="1"/><MySQL Quota="Unlimited" Available="Unlimited"/><LotusDomino Quota="500" Available="499" Used="1"/><LotusNotes Quota="300" Available="299" Used="1"/><InFileDelta Quota="500" Available="499" Used="1"/><VolumeShadowCopy Quota="500" Available="499" Used="1"/><DeltaMerge Quota="500" Available="499" Used="1"/></License></pre> <p>If there is an error, returns <err>%ERROR_MESSAGE%</err></p>			
<p>Where</p> <p>ProductName = product name of AhsayOBS</p> <p>ObsVersion = version of AhsayOBS</p> <p>ExpiryDate = expiry date of AhsayOBS</p> <p>SupportExpiryDate = support expiry date of AhsayOBS</p> <p>MaxQuota = maximum quota of AhsayOBS</p>			

<p>LicenseeName = License name of Ahsay LicenseKey = License key of Ahsay LicenseType = License type of Ahsay Quota = quota Available = unused quota Used = used quota AcbUsedObmUsers = number of AhsayACB users which used the quota of AhsayOBM users OBM = AhsayOBM users ACB = AhsayACB users MSEExchange = MS Exchange Brick level module MSEExchangeMail = MS Exchange Mail level module MSSQL = MSSQL module OracleUsers = Oracle module MySQL = MySQL module LotusDomino = Lotus Domino module LotusNotes = Lotus Notes module InFileDelta = In-file delta module VolumeShadowCopy = Volume shadow copy module DeltaMerge = Delta Merge module</p>
Example:
<p>http://BACKUP_SERVER/obs/api/GetLicense.do?SysUser=system&SysPwd=system</p>
<p>http://BACKUP_SERVER/obs/api/GetLicense.do?SysUser=system&SysPwd=system&Host=obs.yourserver.com</p>

24.23 Get Replication Mode

The following table describes all information required to invoke the [List Replication Mode] API to get the mode of replication available within AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/GetReplicationMode.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
Host	String	(Optional. Use with AhsayRDR only) AhsayOBS's URL	
Return Value:			
<p>If successful, returns <code><Replication Mode="DISABLED"/></code> Or <code><Replication Mode="UNSYNC" File="D:\Test-Data\obs52\user\kwong\files\1194504073875\Current\0x5f\0x3d\0xd2\0xc3\1103301195"/></code> Or <code><Replication Mode="SYNC" File="D:\Test-Data\obs52\user\kwong\files\1194504073875\Current\0x5f\0x3d\0xd2\0xc3\1103301195"/></code> Or <code><Replication Mode="LOGGING" File="D:\Test-Data\obs52\system\logfiles\log0001.alf"/></code></p> <p>If there is an error, returns <code><err>%ERROR_MESSAGE%</err></code></p>			
<p>Where Mode = mode of replication as follow: 1. DISABLED = disabled replication 2. LOGGING = logging mode 3. UNSYNC = un-synchronization mode 4. SYNC = synchronization mode File = current replicating file</p>			
Example:			
http://BACKUP_SERVER/obs/api/GetReplicationMode.do?SysUser=system&SysPwd=system			
http://BACKUP_SERVER/obs/api/GetReplicationMode.do?SysUser=system&SysPwd=system&Host=obs.yourserver.com			

24.24 Send Forgot Password Email

The following table describes all information required to invoke the [Send Forgot Password Email] API to invoke the sending forgot password email operation in AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/SendForgotPwdEmail.do			
Available since version:			
Pre-v6.0			
Parameters:			
	Key	Value	Descriptions
	SysUser	String	AhsayOBS's System Username
	SysPwd	String	AhsayOBS's System Password
	LoginName	String	Login name of the use
Return Value:			
If successful, returns <Reply><Success/></Reply> If there is an error, returns <err>%ERROR_MESSAGE%</err>			
Example:			
http://BACKUP_SERVER/obs/api/SendForgotPwdEmail.do?SysUser=system&SysPwd=system&LoginName=test			

24.25 Delete Backup File

The following table describes all information required to invoke the [Delete Backup File] API to delete backup file in AhsayOBS by a given directory.

URL:			
http://BACKUP_SERVER/obs/api/DeleteBackupFile.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	Login name of the use	
BackupSetName	String	A backup set Name	
InBackupJob	String	A backup job ID (Date when the file was last updated).	
Path	String	{ T F I D C CD LC LD } T - Directory F - Full Backup File (or simply a file) I - Incremental delta file D - Differential delta file C - Checksum file for the full file CD - Checksum file for the delta (both incremental and differential) file LC - Link of checksum file (same content but may contain different file permission or full path) LD - Link of backup data file (same content but may contain different file permission or full path)	
BackupByJob	String	A backup Job ID (Date when the file was uploaded)	
Return Value:			
If successful, returns <Reply><Success/></Reply>			
If there is an error, returns <err>%ERROR_MESSAGE%</err>			
Example:			
http://BACKUP_SERVER/obs/api/DeleteBackupFile.do?SysUser=system&SysPwd=system&LoginName=john&BackupSetName=BackupSet-0&InBackupJob=Current&Path=&Type=D&BackupByJob=2007-01-08-16-02-07			

24.26 Add Advertisement

The following table describes all information required to invoke the [Add Advertisement] API to add a new advertisement to AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/AddAdvertisement.do			
Available since version:			
v6.1.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
AdvertisementName	String	The Name of the new Advertisement	
DisplayTime	String	The time in seconds to display, must be an even number between 2 and 60.	
Target	String	The target URL	
Text	String	The text message to be displayed.	
TextAnimation	String	Text message animation { scroll-left scroll-right none }	
TextAlign	String	Text message alignment { Left Right Center }	
Tracking	Boolean	Whether to enable tracking or not. { Y N }	
AdGroupList	String	The URL of an GIF image, destination file must have .GIF extension	
SwfImage	String	The URL of an SWF image, destination file must have .SWF extension	
Host	String	(Optional. Use with AhsayRDR only) AhsayOBS's URL	
Return Value:			
If successful, returns			
<code><Advertisement ID="1275547136700" Name="New" /></code>			
If there is an error, returns <code><err>%ERROR_MESSAGE%</err></code>			
where ID = Advertisement ID Name = Advertisement name			
Example:			
http://BACKUP_SERVER/obs/api/AddAdvertisement.do?SysUser=system&SysPwd=system&AdvertisementName=New&DisplayTime=8&Target=abc.abc.com&Text=123456&TextAnimation=scroll-			
http://BACKUP_SERVER/obs/api/AddAdvertisement.do?SysUser=system&SysPwd=system&AdvertisementName=New&DisplayTime=8&Target=abc.abc.com&Text=123456&TextAnimation=scroll-			

right&TextAlign=center&Tracking=Y&AdGroupList=1275362087428,1275297492353&GifImage=D:\Pic\test.GIF&SwfImage=D:\Pic\test.SWF&Host=obs.yourserver.com

24.27 List Advertisements

The following table describes all information required to invoke the [List Advertisement] API to get a list of all advertisements at AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/ListAdvertisement.do			
Available since version:			
v6.1.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
AdvertisementID	Number	The ID of an advertisement. If provided, only the specified Advertisement will be Listed.	
AdvertisementNameOnly	Boolean	Whether to display names only or full advertisement details { Y N }	
Host	String	(Optional. Use with AhsayRDR only) AhsayOBS's URL.	
Return Value:			
If successful, returns			
<pre><Advertisements> <Advertisement ID="1275443024656" Name="Advert001" AdGroupList="1275362087428,1275297492353" StartDate="1275443024656" Text="This is a test" TextAnimation="scroll-left" TextAlign="left" Target="www.yahoo.com" Tracking="N" DisplayTime="16" Hits="0/0/0" /> </Advertisements></pre>			
If there is an error, returns <err>%ERROR_MESSAGE%</err>			
where ID = Advertisement ID Name = Advertisement name AdGroupList = The list of associated AdGroups StartDate= The starting date of this advertisement. Text = The text message to be displayed			

<p>TextAnimation = Text message animation { scroll-left scroll-right none }</p> <p>TextAlign = Text message alignment { Left Right Center }</p> <p>Target = The target URL</p> <p>Tracking = Whether to enable tracking or not</p> <p>DisplayTime = The time in seconds to display</p> <p>Hits = The number of times your users clicked this advertisement. The values are { Hits within 1 day Hits within the last 7 days Hits within the last 30 days }</p>
Example:
http://BACKUP_SERVER/obs/api/ListAdvertisement.do?SysUser=system&SysPwd=system&AdvertisementNameOnly=Y&AdvertisementID=1275443024656
http://BACKUP_SERVER/obs/api/ListAdvertisement.do?SysUser=system&SysPwd=system&AdvertisementNameOnly=Y&AdvertisementID=1275443024656&Host=obs.yourserver.com

24.28 Modify Advertisement

The following table describes all information required to invoke the [Modify Advertisement] API to modify an advertisement at AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/ModifyAdvertisement.do			
Available since version:			
v6.1.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
AdvertisementID	Number	The Advertisement ID	
AdvertisementNameOnly	String	The name of the Advertisement	
DisplayTime	Number	The time in seconds to display, must be an even number between 2 and 60.	
Target	String	The target URL.	
Text	String	The text message to be displayed.	
TextAnimation	String	Text message animation { scroll-left scroll-right none }	
TextAlgin	String	Text message alignment { Left Right Center }	
Tracking	Boolean	Whether to enable tracking or not. { Y N }	
AdGroupList	String	Advertisement group e.g. { ALL NONE <AdgroupID> }, accept multiple inputs each separated by a comma.	
ResetStats	Boolean	Whether to reset the hit counts of the advertisement. { Y N }	
GifImage	String	The URL of a GIF image, destination file must have .GIF extension.	

SwfImage	String	The URL of a SWF image, destination file must have .SWF extension.
Host	String	(Optional. Use with AhsayRDR only) AhsayOBS's URL
Return Value:		
If successful, returns <OK/> If there is an error, returns <err>%ERROR_MESSAGE%</err>		
Example:		
http://BACKUP_SERVER/obs/api/ModifyAdvertisement.do?SysUser=system&SysPwd=system&AdvertisementID=1275443024656&AdvertisementName=Advert001&DisplayTime=16&Target=www.yahoo.com&Text=Testing&TextAnimation=scroll-left&TextAlign=left&Tracking=N&AdGroupList=ALL&ResetStats=Y&GifImage=D:\Pic\test.GIF&SwfImage=D:\Pic\test.SWF		
http://BACKUP_SERVER/obs/api/ModifyAdvertisement.do?SysUser=system&SysPwd=system&AdvertisementID=1275443024656&AdvertisementName=Advert001&DisplayTime=16&Target=www.yahoo.com&Text=Testing&TextAnimation=scroll-left&TextAlign=left&Tracking=N&AdGroupList=ALL&ResetStats=Y&GifImage=D:\Pic\test.GIF&SwfImage=D:\Pic\test.SWF&Host=obs.yourserver.com		

24.29 Delete Advertisement

The following table describes all information required to invoke the [Delete Advertisement] API to delete an advertisement from AhsayOBS.

URL:		
http://BACKUP_SERVER/obs/api/DeleteAdvertisement.do		
Available since version:		
v6.1.0.0		
Parameters:		
Key	Value	Descriptions
SysUser	String	AhsayOBS's System Username
SysPwd	String	AhsayOBS's System Password
AdvertisementID	Number	The Advertisement ID
Host	String	(Optional. Use with AhsayRDR only) AhsayOBS's URL
Return Value:		
If successful, returns <OK/> If there is an error, returns <err>%ERROR_MESSAGE%</err>		
Example:		
http://BACKUP_SERVER/obs/api/DeleteAdvertisement.do?SysUser=system&SysPwd=system&AdvertisementID=1275374722809		
http://BACKUP_SERVER/obs/api/DeleteAdvertisement.do?SysUser=system&SysPwd=system&AdvertisementID=1275374722809&Host=obs.yourserver.com		

24.30 Add AdGroup

The following table describes all information required to invoke the [Add AdGroup] API to add a new AdGroup to AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/AddAdGroup.do			
Available since version:			
v6.1.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
AdGroupName	Number	The AdGroup's name	
Host	String	(Optional. Use with AhsayRDR only) AhsayOBS's URL	
Return Value:			
If successful, returns <OK/> If there is an error, returns <err>%ERROR_MESSAGE%</err>			
Example:			
http://BACKUP_SERVER/obs/api/AddAdGroup.do?SysUser=system&SysPwd=system&AdGroupID=1275382280645			
http://BACKUP_SERVER/obs/api/AddAdGroup.do?SysUser=system&SysPwd=system&AdGroupID=1275382280645&Host=obs.yourserver.com			

24.31 List AdGroups

The following table describes all information required to invoke the [List AdGroup] API to get a list of all AdGroups at AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/ListAdGroups.do			
Available since version:			
v6.1.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
Host	String	(Optional. Use with AhsayRDR only) AhsayOBS's URL	
Return Value:			
If successful, returns <AdGroups> <AdGroup ID="1" Name="Default" /> <AdGroup ID="1275297492353" Name="Test2" /> <AdGroup ID="1275297494619" Name="Test3" /> <AdGroup ID="1275297497275" Name="Test4" />			

<pre><AdGroup ID="1275362087428" Name="Test1" /> </AdGroups></pre> <p>If there is an error, returns <err>%ERROR_MESSAGE%</err></p>
Example:
http://BACKUP_SERVER/obs/api/ListAdGroups.do?SysUser=system&SysPwd=system
http://BACKUP_SERVER/obs/api/ListAdGroups.do?SysUser=system&SysPwd=system&Host=obs.yourserver.com

24.32 Modify AdGroup

The following table describes all information required to invoke the [Modify AdGroup] API to modify an AdGroup at AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/ModifyAdGroup.do			
Available since version:			
v6.1.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
AdGroupID	Number	The AdGroup's ID	
AdGroupName	String	The AdGroup's name	
Host	String	(Optional. Use with AhsayRDR only) AhsayOBS's URL	
Return Value:			
If successful, returns <OK/>			
If there is an error, returns <err>%ERROR_MESSAGE%</err>			
Example:			
http://BACKUP_SERVER/obs/api/ModifyAdGroup.do?SysUser=system&SysPwd=system&AdGroupID=1275382280645&AdGroupName=TestingAdGroup2			
http://BACKUP_SERVER/obs/api/ModifyAdGroup.do?SysUser=system&SysPwd=system&AdGroupID=1275382280645&AdGroupName=TestingAdGroup2&Host=obs.yourserver.com			

24.33 Delete AdGroup

The following table describes all information required to invoke the [Delete AdGroup] API to delete an AdGroup from AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/DeleteAdGroup.do			
Available since version:			
Pre-v6.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
AdGroupID	Number	The AdGroup's ID	
Host	String	(Optional. Use with AhsayRDR only) AhsayOBS's URL	
Return Value:			
If successful, returns <OK/> If there is an error, returns <err>%ERROR_MESSAGE%</err>			
Example:			
http://BACKUP_SERVER/obs/api/DeleteAdGroup.do?SysUser=system&SysPwd=system&AdGroupID=1275382280645			
http://BACKUP_SERVER/obs/api/DeleteAdGroup.do?SysUser=system&SysPwd=system&AdGroupID=1275382280645&Host=obs.yourserver.com			

24.34 Run Backup

The following table describes all information required to invoke the [Run backup set] API to initiate backup for a specific backup set.

URL:			
http://BACKUP_SERVER/obs/api/RunBackup.do			
Available since version:			
6.3.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	User's login name	
BackupSetID	String	The backup set ID	
BackupType	String	The backup type: {empty} when backup set type is "File/MySQL Database Server/Lotus Notes/System State/Microsoft Exchange Mail Level Backup/Microsoft Windows System Backup" { Database Log } when backup set type is "Microsoft Exchange Server/Oracle Database Server/Lotus Domino" { Database Differential Log } when backup set type is "Microsoft SQL Server" { Complete Differential Incremental } when backup set type is "ShadowProtect System Backup"	
CancelBackup	String	(Optional) Whether to cancel backup for the specific backup set.	
Return Value:			
If successful, returns <OK/> If there is an error, returns <err>%ERROR_MESSAGE%</err>			
Example:			
http://BACKUP_SERVER/obs/api/RunBackup.do?SysUser=system&SysPwd=system&LoginName=2916_tester&BackupSetID=1280458302800&BackupType=COMPLETE&CancelBackup=N			

24.35 Get Backup Job Progress

The following table describes all information required to invoke the [Get Backup Job Progress] API to retrieve the backup job progress.

URL:			
http://BACKUP_SERVER/obs/api/GetBackupJobProgress.do			
Available since version:			
v6.3.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	(Optional) The user's login name. If specified, only the backup jobs of the user is displayed otherwise all backup jobs are displayed.	
BackupSetID	String	The ID of the backup set	
BackupJobID	String	The ID of the backup Job	
Return Value:			
If successful, returns			
<pre><BackupJob ID="2010-11-30-19-59-03" LoginName="StanleyLee" StartTime="2010-11-30 19:59:05" EndTime="2010-11-30 19:59:17" BackupSetID="1289447020102" BackupSetName="testing" CurrentFilename="C:\Program Files\Kaspersky Lab\NetworkAgent\Products\E07A4C8CB7A5029D3AA8E87E542DB0D5\~pr ivdata.~dat~2" FileUploadTime="2010-11-30 19:59:13" CurrentFileCount="26" TotalFileCount="26" UploadedFileSize="1241247" TotalFileSize="1241247"/></pre>			
If the backup is still running, the value of EndTime should become "1970-01-01 08:00:00"			
If there is an error, it returns <err>%ERROR_MESSAGE%</err>			
where under			
Tag <BackupJob>			
ID = backup job ID			
LoginName = user name			
StartTime = job start time			
EndTime = job end time			
BackupSetID = backup set ID			
BackupSetName = Backup set Name			
CurrentFilename = Current uploading filename			
CurrentFileCount = Number of uploaded files (including uploading file)			
TotalFileCount = Number of total uploaded files			
UploadedFileSize = Size of uploaded files			
TotalFileSize = Size of total uploaded files			

	FileUploadTime= Start time of uploading file (yyyy-MM-dd HH:mm:ss)
Example:	
	http://192.168.6.172:9090/obs/api/GetBackupJobProgress.do?SysUser=system&SysPwd=system&LoginName=StanleyLee&BackupSetID=1291008667235&BackupJobID=2010-11-30-10-39-01

24.36 Add User Group

The following table describes all information required to invoke the [Add User Group] API to add a user group.

URL:			
http://BACKUP_SERVER/obs/api/AddUserGroup.do			
Available since version:			
v6.3.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
UserGroupName	String	The name of the User Group (Currently, API only supports modifications related to backup user groups.)	
LoginNameList	String	Users assign to the group e.g. [LoginName], accept multiple inputs, each separated by a comma, i.e. user1, user2, user3,..etc It is highly recommended to use URL encoding for long Login Names (e.g. User2#12345 -> User2%2312345)	
Return Value:			
If successful, returns:			
<code><UserGroup ID="1275547136700" Name="User Group A" /></code>			
If there is an error, returns <code><err>%ERROR_MESSAGE%</err></code>:			
i. User Group Name already exists on AhsayOBS			
<code><err>[PolicyControlException.DuplicatedUserGroupNameException] User Group Name '%GROUP_NAME%' is used</err></code>			
ii. User name does not exist on AhsayOBS or an incorrect user specified			
<code><err>[UserCacheManager.NoSuchUserExpt] User '%USER_NAME%' not found.</err></code>			
Example:			
<code>http://BACKUP_SERVER/obs/api/AddUserGroup.do?SysUser=system&SysPwd=system&UserGroupName=XYZ</code>			
http://BACKUP_SERVER/obs/api/AddUserGroup.do?SysUser=system&SysPwd=system&UserGroupName=ABC&LoginNameList=GroupUser1,GroupUser2%2312345			

24.37 List User Group

The following table describes all information required to invoke the [List User Group] API to list all the available user groups on AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/ListUserGroups.do			
Available since version:			
v6.3.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
UserGroupID	Number	The ID of the User Group. If provided, only the specified User Group will be listed. (Currently, API only supports modifications related to backup user groups.)	
LoginName	String	Filter listed User Group by specific backup user (Only effective if UserGroupID has not been specified).	
UserGroupOnly	Boolean	Whether to display User Group only or full User Group details. { Y N }	
Return Value:			
<p>If successful, returns (UserGroupOnly = N)</p> <pre> <UserGroups> <UserGroup ID="1275897475792" Name="User Group - 3" Type="backup-user" Owner="" > <Users> <User Name="GroupUser1" /> </Users> <PolicyGroups> <PolicyGroup ID="1275897783056" Name="Policy Group - 2" /> </PolicyGroups> </UserGroup> </UserGroups> ... </pre> <p>If successful, returns (UserGroupOnly = Y) or if UserGroupOnly is not specified</p> <pre> <UserGroups> <UserGroup ID="1243569613625" Name="User Group - Read Only" Type="backup-user" Owner="" /> <UserGroup ID="1275895771498" Name="Testing Group" Type="backup-user" Owner="" /> <UserGroup ID="1275897475792" Name="User Group - 3" </pre>			

	<p>Type="backup-user" Owner=""/ > </UserGroups></p> <p>If there is an error, returns <err>%ERROR_MESSAGE%</err></p>
Example:	
	<p>http://BACKUP_SERVER/obs/api/ListUserGroups.do?SysUser=system&SysP wd=system</p> <p><a href="http://BACKUP_SERVER/obs/api/ListUserGroups.do?SysUser=system&SysP
wd=system&UserGroupOnly=Y&UserGroupID=1275443024656%LoginName">http://BACKUP_SERVER/obs/api/ListUserGroups.do?SysUser=system&SysP wd=system&UserGroupOnly=Y&UserGroupID=1275443024656%LoginName</p>

24.38 Modify User Group

The following table describes all information required to invoke the [Modify User Group] API to modify the user group.

URL:		
http://BACKUP_SERVER/obs/api/ModifyUserGroup.do		
Available since version:		
v6.3.0.0		
Parameters:		
Key	Value	Descriptions
SysUser	String	AhsayOBS's System Username
SysPwd	String	AhsayOBS's System Password
UserGroupID	Number	The ID of the User Group. (Currently, API only supports modifications related to backup user groups.)
UserGroupName	String	The name of the User Group
Mode	String	This defines whether the API will add or delete user from the User Group { A D }. (Where A = add , D = delete)
LoginNameList	String	List of users that will be assigned to the User Group. [LoginName], accepts multiple inputs, each separated by a comma. Please note that LoginNameList is ONLY compatible with this API in ADD mode.It is highly recommended to use URL encoding for login names
LoginName	String	The login name of a specific user that will be assigned / removed from the User Group depending on the value of Mode. It is highly recommended to use URL encoding for login names
Return Value:		
If successful, returns <OK/> If there is an error, returns <err>%ERROR_MESSAGE%</err>		
Example:		
http://BACKUP_SERVER/obs/api/ModifyUserGroup.do?SysUser=system&SysPwd=system&UserGroupID=1275895771498&UserGroupName=Testing_Group&LoginNameList=GroupUser2&LoginName=GroupUser1&Mode=A		
http://BACKUP_SERVER/obs/api/ModifyUserGroup.do?SysUser=system&SysPwd=system&UserGroupID=1275895771498&UserGroupName=Testing_Group&LoginNameList=Testuser1,Testuser2&Mode=A		
http://BACKUP_SERVER/obs/api/ModifyUserGroup.do?SysUser=system&SysPwd=system&UserGroupID=1275895771498&UserGroupName=Testing_Group&LoginName=Testuser&Mode=A		

24.39 Delete User Group

The following table describes all information required to invoke the [Delete User Group] API to delete a user group.

URL:		
http://BACKUP_SERVER/obs/api/DeleteUserGroup.do		
Available since version:		
v6.3.0.0		
Parameters:		
Key	Value	Descriptions
SysUser	String	AhsayOBS's System Username
SysPwd	String	AhsayOBS's System Password
UserGroupID	Number	The ID of the User Group. (Currently, API only supports modifications related to backup user groups.)
Return Value:		
If successful, returns <OK/>		
If there is an error, returns <err>%ERROR_MESSAGE%</err>		
i. Incorrect UserGroupID specified		
<err>[Error] Parameter UserGroupID, xxxxxxxxx does not existed!</err>		
ii. The UserGroupID parameter was omitted from the API or the value of the UserGroupID is empty		
<err>[Error] Parameter UserGroupID is null/empty!</err>		
Example:		
http://BACKUP_SERVER/obs/api/DeleteUserGroup.do?SysUser=system&SysPwd=system&UserGroupID=1275895280730		

24.40 List Policy Groups

The following table describes all information required to invoke the [List Policy Group] API to list user assigned policy groups.

URL:			
http://BACKUP_SERVER/obs/api/ListPolicyGroups.do			
Available since version:			
v6.3.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
LoginName	String	User's Login Name	
Type	String	User's type, e.g. [backup-user] (Currently, API only supports modifications related to backup user groups.)	
PolicyGroupNameOnly	String	(Optional) Only policy ID and policy name will be listed. { Y N }	
Return Value:			
<p>If successful, returns</p> <pre><PolicyGroups> <PolicyGroup PolicyGroupID="1282186302196" PolicyGroupName="Policy Group - 4634 -1"> <SharedQuota Enabled="Y" SharedSize="0" MaxPercentage="0"/> <DefaultBackupSets> <DefaultObmFileWindowsBackupSet ID="-1276842815367" Name=" BackupSet- Windows - File "/> <DefaultObmFileMacBackupSet ID="-1282618475562" Name="BackupSet- Mac - File"/> <DefaultObmFileLinuxBackupSet ID="-1282618461980" Name="BackupSet- Linux - File"/> <DefaultObmMsSqlWindowsBackupSet ID="- 1282618486349" Name="BackupSet- MSSql - Windows"/> <DefaultObmMsExchangeWindowsBackupSet ID="- 1282618503663" Name="BackupSet- Windows - MsExchange"/> <DefaultObmOracleWindowsBackupSet ID="- 1282618537197" Name="BackupSet- Windows - Oracle"/> <DefaultObmOracleMacBackupSet ID="-1282618572791" Name="BackupSet- Mac - Oracle "/> <DefaultObmOracleLinuxBackupSet ID="-1282618554292" Name="BackupSet- Linux - Oracle "/> <DefaultObmMySqlWindowsBackupSet ID="- 1282618598504" Name="BackupSet- Windows - MySql "/> <DefaultObmMySqlMacBackupSet ID="-1282618634395" Name="BackupSet- Mac - MySQL "/> <DefaultObmMySqlLinuxBackupSet ID="-1282618611321" Name="BackupSet- Linux - MySQL"/> <DefaultObmDominoWindowsBackupSet ID="-</pre>			

```

1282618650444" Name="BackupSet- Windows - Domino"/>
    <DefaultObmDominoLinuxBackupSet ID="-
1282618667804" Name="BackupSet- Linux - Domino"/>
    <DefaultObmNotesWindowsBackupSet ID="-
1282618683603" Name="BackupSet- Windows - Notes"/>
    <DefaultObmSystemStateWindowsBackupSet ID="-
1282618697264" Name="BackupSet- Windows - System State"/>
    <DefaultObmMsExchangeMailWindowsBackupSet ID="-
1282618717012" Name="BackupSet- Windows - MsExchange - Mail"/>
    <DefaultObmShadowProtectWindowsBackupSet ID="-
1282618736574" Name="BackupSet- Windows - Shadow Protect"/>
    <DefaultObmMsWindowsWindowsBackupSet ID="-
1282618760663" Name="BackupSet- Windows - Windows"/>
    <DefaultAcbWindowsBackupSet ID="-1278558712322"
Name="BackupSet-4748_acb"/>
    <DefaultAcbMacBackupSet ID="-1282618821970"
Name="BackupSet- Mac"/>
    <EnforcementObmFileWindowsBackupSet ID="-
1282618858299" Name="BackupSet-0"/>
    <EnforcementObmFileMacBackupSet ID="-1282618475562"
Name="BackupSet- Mac - File"/>
    <EnforcementObmFileLinuxBackupSet ID="-
1282618461980" Name="BackupSet- Linux - File"/>
    <EnforcementObmMsSqlWindowsBackupSet ID="-
1282618858300" Name="BackupSet- Windows - MSSql "/>
    <EnforcementObmMsExchangeWindowsBackupSet ID="-
1282618503663" Name="BackupSet- Windows - MsExchange"/>
    <EnforcementObmOracleWindowsBackupSet ID="-
1282618537197" Name="BackupSet- Windows - Oracle"/>
    <EnforcementObmOracleMacBackupSet ID="-
1282618572791" Name="BackupSet- Mac - Oracle"/>
    <EnforcementObmOracleLinuxBackupSet ID="-
1282618554292" Name="BackupSet- Linux - Oracle"/>
    <EnforcementObmMySqlWindowsBackupSet ID="-
1282618598504" Name="BackupSet- MySql - Windows"/>
    <EnforcementObmMySqlMacBackupSet ID="-
1282618634395" Name="BackupSet- Mac - MySQL"/>
    <EnforcementObmMySqlLinuxBackupSet ID="-
1282618611321" Name="BackupSet- Linux - MySQL"/>
    <EnforcementObmDominoWindowsBackupSet ID="-
1282618650444" Name="BackupSet- Windows - Domino"/>
    <EnforcementObmDominoLinuxBackupSet ID="-
1282618667804" Name="BackupSet- Linux - Domino"/>
    <EnforcementObmNotesWindowsBackupSet ID="-
1282618683603" Name="BackupSet- Windows - Notes"/>
    <EnforcementObmSystemStateWindowsBackupSet ID="-
1282618697264" Name="BackupSet- Windows - System State"/>
    <EnforcementObmMsExchangeMailWindowsBackupSet
ID="-1282618717012" Name="BackupSet- Windows - MsExchange -
Mail"/>
    <EnforcementObmShadowProtectWindowsBackupSet ID="-

```

```

1282618736574" Name="BackupSet- Windows - Shadow Protect"/>
    <EnforcementObmMsWindowsBackupSet ID="-
1282618760663" Name="BackupSet- Windows - Windows"/>
    <EnforcementAcbWindowsBackupSet ID="-
1278558712322" Name="BackupSet-4748_acb"/>
    <EnforcementAcbMacBackupSet ID="-1282618821970"
Name="BackupSet- Mac"/>
    </DefaultBackupSets>
    <PolicyControls>
      <PolicyControl ID="OBS-UUP-10001" Name="Manage User-User-User
Profile Menu" ShowRead="Y" ShowWrite="N" ShowExecute="N"
ShowDelete="N" EnableRead="N" EnableWrite="N" EnableExecute="N"
EnableDelete="N"/>
      <PolicyControl ID="OBS-UUP-10002" Name="Manage
User-User-User Profile-User Summary" ShowRead="Y" ShowWrite="N"
ShowExecute="N" ShowDelete="N" EnableRead="N" EnableWrite="N"
EnableExecute="N" EnableDelete="N"/>
      <PolicyControl ID="OBS-UUP-10003" Name="Manage
User-User-User Profile-Alias" ShowRead="Y" ShowWrite="Y"
ShowExecute="N" ShowDelete="N" EnableRead="N" EnableWrite="N"
EnableExecute="N" EnableDelete="N"/>
      <PolicyControl ID="OBS-UUP-10004" Name="Manage
User-User-User Profile-Language" ShowRead="Y" ShowWrite="Y"
ShowExecute="N" ShowDelete="N" EnableRead="N" EnableWrite="N"
EnableExecute="N" EnableDelete="N"/>
      <PolicyControl ID="OBS-UUP-10005" Name="Manage
User-User-User Profile-Timezone" ShowRead="Y" ShowWrite="Y"
ShowExecute="N" ShowDelete="N" EnableRead="N" EnableWrite="N"
EnableExecute="N" EnableDelete="N"/>
      <PolicyControl ID="OBS-UUP-10006" Name="Manage
User-User-User Profile-Contact" ShowRead="Y" ShowWrite="Y"
ShowExecute="N" ShowDelete="N" EnableRead="N" EnableWrite="N"
EnableExecute="N" EnableDelete="N"/>
      <PolicyControl ID="OBS-UUP-10007" Name="Manage
User-User-User Profile-Add-on Modules" ShowRead="Y" ShowWrite="N"
ShowExecute="N" ShowDelete="N" EnableRead="N" EnableWrite="N"
EnableExecute="N" EnableDelete="N"/>
      <PolicyControl ID="OBS-UUP-10008" Name="Manage User-
User-User Profile-Quota" ShowRead="Y" ShowWrite="N"
ShowExecute="N" ShowDelete="N" EnableRead="N" EnableWrite="N"
EnableExecute="N" EnableDelete="N"/>
      <PolicyControl ID="OBS-UUP-10009" Name="Manage User-
User-User Profile-Update Reset Button" ShowRead="Y" ShowWrite="Y"
ShowExecute="N" ShowDelete="N" EnableRead="N" EnableWrite="N"
EnableExecute="N" EnableDelete="N"/>
    </PolicyControls>
    <GlobalFilters>
      <ObmFileWindowsNormalFilter ID="" Name=""/>
      <ObmFileMacNormalFilter ID="" Name=""/>
      <ObmFileLinuxNormalFilter ID="" Name=""/>
      <ObmDominoWindowsNormalFilter ID="" Name=""/>

```

```

    <ObmDominoLinuxNormalFilter ID="" Name=""/>
    <ObmNotesWindowsNormalFilter ID="" Name=""/
    <ObmFileWindowsCdpFilter ID="" Name=""/>
    <ObmFileMacCdpFilter ID="" Name=""/>
    <ObmFileLinuxCdpFilter ID="" Name=""/>
    <AcbFileWindowsNormalFilter ID="-11282635326290" Name="Filter
Windows"/>
    <AcbFileMacNormalFiler ID="-41282635346189" Name="Filter Mac"/>
    </GlobalFilters>
  </PolicyGroup>
</PolicyGroups>
If there is an error, returns <err>%ERROR_MESSAGE%</err>

```

Where

PolicyGroupID = policy group id

PolicyGroupName = policy group name

Tag <Shared Quota>

Enabled = share disk quota enabled { Y | N }

SharedSize = disk quota shared size

MaxPercentage = Maximum percentage of disk quota shared

Tag <Default Backup Sets>

ID = default backup set ID

Name = default backup set name

DefaultObmFileWindowsBackupSet = OBM file default backup set for windows

DefaultObmFileMacBackupSet = OBM file default backup set for mac

DefaultObmFileLinuxBackupSet = OBM file default backup set for linux

DefaultObmMsSqlWindowsBackupSet = OBM Microsoft SQL server default backup set for windows

DefaultObmMsExchangeWindowsBackupSet = OBM Microsoft exchange server default backup set for windows

DefaultObmOracleWindowsBackupSet = OBM oracle default backup set for windows

DefaultObmOracleMacBackupSet = OBM Oracle database server default backup set for mac

DefaultObmOracleLinuxBackupSet = OBM Oracle database server default backup set for linux

DefaultObmMySqlWindowsBackupSet = OBM MySQL default backup set for windows

DefaultObmMySqlMacBackupSet = OBM MySQL default backup set for mac

DefaultObmMySqlLinuxBackupSet = OBM MySQL default backup set for linux

DefaultObmDominoWindowsBackupSet = OBM Lotus Domino default backup set for windows

DefaultObmDominoLinuxBackupSet = OBM Lotus Domino default backup set for linux

DefaultObmNotesWindowsBackupSet = OBM Lotus Notes default backup set for windows

DefaultObmSystemStateWindowsBackupSet = OBM System State

<p>default backup set for windows DefaultObmMsExchangeMailWindowsBackupSet = OBM Microsoft Exchange Mail default backup set for windows DefaultObmShadowProtectWindowsBackupSet = OBM Shadow Protect System default backup set for windows DefaultObmMsWindowsWindowsBackupSet = OBM Microsoft Windows System default backup set for windows DefaultAcbWindowsBackupSet = ACB File default backup set for windows DefaultAcbMacBackupSet = ACB File default backup set for mac EnforcementObmFileWindowsBackupSet = OBM File default backup set for windows EnforcementObmFileMacBackupSet = OBM File enforcement backup set for mac EnforcementObmFileLinuxBackupSet = OBM File enforcement backup set for linux EnforcementObmMsSqlWindowsBackupSet = OBM Microsoft SQL enforcement backup set for windows EnforcementObmMsExchangeWindowsBackupSet = OBM Microsoft Exchange enforcement backup set for windows EnforcementObmOracleWindowsBackupSet = OBM Oracle enforcement backup set for windows EnforcementObmOracleMacBackupSet = OBM Oracle enforcement backup set for mac EnforcementObmOracleLinuxBackupSet = OBM Oracle enforcement backup set for linux EnforcementObmDominoWindowsBackupSet = OBM Lotus Domino enforcement backup set for windows EnforcementObmDominoLinuxBackupSet = OBM Lotus Domino enforcement backup set for linux EnforcementObmNotesWindowsBackupSet = OBM Lotus Notes enforcement backup set for windows EnforcementObmSystemStateWindowsBackupSet = OBM System State enforcement backup set for windows EnforcementObmMsExchangeMailWindowsBackupSet = OBM Microsoft Exchange Mail enforcement backup set for windows EnforcementObmShadowProtectWindowsBackupSet = OBM Shadow Protect enforcement backup set for windows EnforcementObmMsWindowsBackupSet = OBM Microsoft Windows enforcement backup set for windows EnforcementAcbWindowsBackupSet = ACB File enforcement backup set for windows EnforcementAcbMacBackupSet = ACB File enforcement backup set for linux</p> <p>Tag <Policy Controls> ID = policy control ID Name = policy control name ShowRead = show read permission ShowWrite = show write permission ShowExecute = show execute permission ShowDelete = show delete permission</p>
--

<p>EnableRead = enable read permission EnableWrite = show write permission EnableExecute = show execute permission</p> <p>Tag <Global Filters> ID = global filter ID Name = global filter name ObmFileWindowsNormalFilter = OBM File normal filter for windows ObmFileMacNormalFilter = OBM File normal filter for mac ObmFileLinuxNormalFilter = OBM File normal filter for linux ObmDominoWindowsNormalFilter = OBM Domino normal filter for windows ObmDominoLinuxNormalFilter = OBM Lotus Domino normal filter for linux ObmNotesWindowsNormalFilter = OBM Lotus Notes normal filter for windows ObmFileWindowsCdpFilter = OBM File cdp filter for windows ObmFileMacCdpFilter = OBM File cdp filter for mac ObmFileLinuxCdpFilter = OBM File cdp filter for linux AcbFileWindowsNormalFilter = ACB normal filter for windows AcbFileMacNormalFilter = ACB normal filter for mac</p>
Example:
<p>http://BACKUP_SERVER/obs/api/ListPolicyGroups.do?SysUser=system&SysPwd=system&LoginName=4632_tester&Type=backup-user&PolicyGroupNameOnly=N</p>

24.41 Add User Groups to Policy Group

The following table describes all information required to invoke the [Add user groups to policy group] within AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/AddUserGroupsToPolicyGroup.do			
Available since version:			
v6.3.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
PolicyGroupID	String	The policy group ID	
UserGroupIDList	String	The user group ID, separated by "," (Currently, API only supports modifications related to backup user groups.)	
Return Value:			
If successful, returns <OK/> If there is an error, returns <err>%ERROR_MESSAGE%</err>			
Example:			
http://BACKUP_SERVER/obs/api/AddUserGroupsToPolicyGroup.do?SysUser=system&SysPwd=system&PolicyGroupID=1280458302800&UserGroupID			

List=1280458287815,1282186204737
--

24.42 Delete User Group from Policy Group

The following table describes all information required to invoke the [Remove user group from policy group] API to remove user groups from policy group within AhsayOBS.

URL:			
http://BACKUP_SERVER/obs/api/DeleteUserGroupFromPolicyGroup.do			
Available since version:			
v6.3.0.0			
Parameters:			
Key	Value	Descriptions	
SysUser	String	AhsayOBS's System Username	
SysPwd	String	AhsayOBS's System Password	
PolicyGroupID	String	The policy group ID	
UserGroupID	String	The user group ID	
Return Value:			
If successful, returns <OK/>			
If there is an error, returns <err>%ERROR_MESSAGE%</err>			
Example:			
http://BACKUP_SERVER/obs/api/DeleteUserGroupFromPolicyGroup.do?SysUser=system&SysPwd=system&PolicyGroupID=1280458302800&UserGroupID=1280458287815			

24.43 Additional APIs

If you need additional APIs to automate your business workflow, please feel free to let us know.

25 Further Information

If you have any question or suggestion about this document, please send an email to our support team via our [Helpdesk Ticketing System](#).

Appendix

Appendix A Supported Language Code

Language Code	Language
bg	Bulgarian
ca	Catalan
cs	Czech
da	Danish
de	German
el	Greek
en	English
es	Spanish
eu	Basque
fi	Finnish
fr	French
hu	Hungarian
is	Icelandic
it	Italian
iw	Hebrew
ja	Japanese
ko	Korean
lt	Lithuanian
nl	Dutch
no	Norwegian
po	Polish
pt_BR	Portuguese (Brazil)
pt_PT	Portuguese (Portugal)
ro	Romanian
ru	Russian
sl	Slovenian
sv	Swedish
th_th	Thai (Thai Digit)
tr	Turkish
zh_CN	Chinese (Simplified)
zh_TW	Chinese (Traditional)

Appendix B Supported Time zone

Timezone String	Timezone Name
GMT-11:00 (WST)	Western Standard Time
GMT-11:00 (NUT)	Niue Time
GMT-11:00 (SST)	Samoa Standard Time
GMT-10:00 (HADT)	Hawaii-Aleutian Daylight Time
GMT-10:00 (HST)	Hawaiian Standard Time
GMT-10:00 (TKT)	Tokelau Time
GMT-10:00 (HST)	Hawaiian Standard Time
GMT-10:00 (CKT)	Cook Islands Time
GMT-10:00 (THAT)	Tahiti Time
GMT-09:00 (AKST)	Alaska Standard Time
GMT-09:00 (GAMT)	Gambier Time
GMT-08:00 (PST)	Pacific Standard Time (North America)
GMT-07:00 (PDT)	Pacific Daylight Time (North America)
GMT-07:00 (MST)	Mountain Standard Time
GMT-07:00 (MDT)	Mountain Day Time
GMT-06:00 (CST)	Central Standard Time
GMT-06:00 (CDT)	Central Daylight Time
GMT-06:00 (EAST)	Easter Island Time
GMT-06:00 (GALT)	Galapagos Time
GMT-05:00 (EST)	Eastern Standard Time (North America)
GMT-05:00 (EDT)	Eastern Daylight Time (North America)
GMT-05:00 (COT)	Colombia Time
GMT-05:00 (ECT)	Ecuador Time
GMT-05:00 (CDT)	Central Daylight Time (North America)
GMT-05:00 (PET)	Peru Time
GMT-05:00 (ACT)	Atlantic/Proto Acre
GMT-05:00 (GMT-05:00)	GMT -05:00
GMT-04:00 (AST)	Atlantic Standard Time
GMT-04:00 (PYT)	Paraguay Time
GMT-04:00 (VET)	Venezuela Time
GMT-04:00 (GYT)	Guyana Time
GMT-04:00 (ADT)	Acre Daylight Time
GMT-04:00 (BOT)	Bolivia Time
GMT-04:00 (AMT)	Armenia Time
GMT-04:00 (CLT)	Chile Time
GMT-04:00 (FKT)	Falkland Islands
GMT-03:00 (ART)	Argentina Time
GMT-03:00 (GFT)	French Guiana Time
GMT-03:00 (BRT)	Brasilia Time
GMT-03:00 (WGST)	West Greenland Summer Time
GMT-03:00 (PMDT)	Pierre & Miquelon Daylight Time
GMT-03:00 (UYT)	Uruguay Time
GMT-03:00 (SRT)	Suriname Time
GMT-02:00 (FNT)	Fernando de Noronha Time
GMT-02:00 (GST)	Gulf Standard Time
GMT-01:00 (EGST)	East Greenland Summer Time

GMT+00:00 (GMT)	Greenwich Mean Time
GMT+00:00 (WET)	Western European Time
GMT+00:00 (WEST)	Western European Summer Time
GMT+00:00 (IST)	Israel Standard Time
GMT+00:00 (BST)	Brazil Standard Time
GMT+00:00 (UTC)	Coordinate Universal Time
GMT+01:00 (CET)	Central European Time
GMT+01:00 (WAT)	West Africa Time
GMT+01:00 (CEST)	Central European Summer Time
GMT+02:00 (EEST)	Eastern European Summer Time
GMT+02:00 (CAT)	Central Africa Time
GMT+02:00 (SAST)	Soft Africa Standard Time
GMT+02:00 (EET)	Eastern European Time
GMT+02:00 (IDT)	Israel Daylight Time
GMT+03:00 (EAT)	East Africa Time
GMT+03:00 (AST)	Acre Standard Time
GMT+03:00 (ADT)	Acre Daylight Time
GMT+03:00 (MSD)	Moscow Daylight Time
GMT+04:00 (AQST)	Aqtau Time
GMT+04:00 (AZST)	Azerbaijan Summer Time
GMT+04:00 (GST)	Gulf Standard Time
GMT+04:00 (GEST)	Georgia Time
GMT+04:00 (AMST)	Armenia Summer Time
GMT+04:00 (SAMST)	Samara Time
GMT+04:00 (SCT)	Seychelles Time
GMT+04:00 (MUT)	Mauritius Time
GMT+04:00 (RET)	Reunion Time
GMT+05:00 (TMT)	Turkmenistan Time
GMT+05:00 (KGST)	Kirgizstan Time
GMT+05:00 (TJT)	Tajikistan Time
GMT+05:00 (PKT)	Pakistan Time
GMT+05:00 (UZT)	Uzbekistan Time
GMT+05:00 (YEKST)	Yekaterinburg Time
GMT+05:00 (IDT)	Indian Standard Time
GMT+05:00 (TFT)	French Southern & Antarctic Lands Time
GMT+05:00 (MVT)	Maldives Time
GMT+06:00 (MAWT)	Mawson Time
GMT+06:00 (LKT)	Lanka Time
GMT+06:00 (BDT)	Bangladesh Time
GMT+06:00 (NOVST)	Novosibirsk Time
GMT+06:00 (BTT)	Bhutan Time
GMT+07:00 (ICT)	Indochina Time
GMT+07:00 (JAVT)	Java Time, Indonesia Time
GMT+07:00 (KRAST)	Krasnoyarsk Time
GMT+07:00 (CXT)	Christmas Island Time
GMT+08:00 (HKT)	Hong Kong Time
GMT+08:00 (CST)	Cuba Standard Time
GMT+08:00 (BNST)	Brunei Time
GMT+08:00 (WST)	West Samoa Time

GMT+08:00 (IRKST)	Irkutsk Time
GMT+08:00 (MYT)	Malaysia Time
GMT+08:00 (PHT)	Philippine Time
GMT+08:00 (SGT)	Singapore Time
GMT+08:00 (BORT)	Borneo Time
GMT+08:00 (ULAT)	Ulan Bator Time
GMT+08:00 (JAYT)	Jayapura Time
GMT+09:00 (KST)	Korean Standard Time
GMT+09:00 (JST)	Japan Standard Time
GMT+09:00 (YAKST)	Yakutsk Time
GMT+09:00 (PWT)	Palau Time
GMT+10:00 (EST)	Eastern Standard Time (Australia)
GMT+10:00 (DDUT)	Dumont-d'Urville Time
GMT+10:00 (VLAST)	Vladivostok Time
GMT+10:00 (ChST)	Chamorro Standard Time
GMT+10:00 (PGT)	Papua New Guinea Time
GMT+10:00 (TRUST)	Truk Time
GMT+11:00 (MAGST)	Magadan Time
GMT+11:00 (VUT)	Vanuatu Time
GMT+11:00 (KOSST)	Kosrae Time
GMT+11:00 (NCT)	New Caledonia Time
GMT+11:00 (PONT)	Ponape Time (Micronesia)
GMT+12:00 (NZST)	New Zealand Standard Time
GMT+12:00 (ANAST)	Anadyr Time
GMT+12:00 (PETST)	Petropavlovsk-Kamchatski Time
GMT+12:00 (FJT)	Fiji Time
GMT+12:00 (TVT)	Tuvalu Time
GMT+12:00 (MHT)	Marshall Islands Time
GMT+12:00 (NRT)	Nauru Time
GMT+12:00 (GILT)	Gilbert Island Time
GMT+12:00 (WAKT)	Wake Time
GMT+12:00 (WFT)	Wallis and Futuna Time

Appendix C Product Documentations

Please visit this [link](#) for the documentations of Ahsay Products.

Appendix D Error Code 1011 and 1012

Internal Error 1011

This error could occur when one of the following conditions is true:

1. The license key has been used on more than one machine.
2. Change of network card of the server machine or moving the AhsayBS system to a new server.

Solution:

In the cases where the license key was used on a second server for testing purposes, please use an evaluation key instead.

Alternatively, please shutdown the AhsayOBS service on the second server, and then contact our Support Engineer with your "License Name" and "License Key", and we shall update the license server to allow your key to be used again.

In the cases where the network card of the server machine is changed, or an AhsayOBS relocation has been performed. Please also contact our Support Engineer with your "License Name" and "License Key", and we shall update the license server to allow your key to be used again.

If the problem still persists, please ensure that there are no connectivity issues from the AhsayOBS server to the internet and that you can connect to lic.ahsay.com with HTTPS from the AhsayOBS backup server.

Please also verify if the machine in concern contain any software that would create virtual MAC address, for example, VPN software. If yes, please disable them such software, and notify us again.

Internal Error 1012

Internal Error 1012 can occur when one of the following conditions is true:

1. The license key has been used on more than one machine.
2. Change of the MAC address, local / remote IP address, or local port that AhsayOBS is installed on.

Solution:

Persistent 1012 license errors can occur if your AhsayOBS server is operating in a network environment where network traffic is routed to the internet via multiple external IP addresses. For example, network load balancing is implemented using, i.e. a dual WAN router, Round Robin routing, or network card with multiple external IP.

For these cases, we would suggest setting up a static route for the server's connection to lic.ahsay.com, so that the remote IP address on the server will remain the same every time a connection to lic.ahsay.com is established.